# **Masterarbeit Grosch Documentation**

Release 0.4c0

**Tobias Grosch** 

# CONTENTS

| 1                   | bacnet package     |                        |    |  |  |  |
|---------------------|--------------------|------------------------|----|--|--|--|
|                     | 1.1                | Subpackages            | 3  |  |  |  |
|                     | 1.2                | Submodules             | 54 |  |  |  |
|                     | 1.3                | bacnet.settings module | 54 |  |  |  |
|                     | 1.4                | Module contents        | 54 |  |  |  |
| 2                   | Indices and tables |                        |    |  |  |  |
| Python Module Index |                    |                        |    |  |  |  |
| Index               |                    |                        |    |  |  |  |

Contents:

CONTENTS 1

2 CONTENTS

**CHAPTER** 

**ONE** 

# **BACNET PACKAGE**

# 1.1 Subpackages

# 1.1.1 bacnet.api package

## **Module contents**

#### **BACnet API Module**

This module provides basic api functionality.

```
class bacnet.api.BACnetAPI(*args)
```

Bases: object

This class unifies all API accessible functions.

create(line)

This function creates a request for the specified command.

Parameters line - command line

Returns request object

## static parse (apdu)

This function returns a parsed dictionary from provided message. :param apdu: message :return: parsed dict

receive (block=True, timeout=None)

This function checks for available incoming requests

## **Parameters**

- block block
- timeout timeout

**Returns** incoming response or None

send (request, block=True, timeout=None)

This function transmits the request.

## **Parameters**

- request outgoing request
- block block
- timeout timeout

Returns request was queued

## 1.1.2 bacnet.app package

## **Subpackages**

bacnet.app.handler package

Submodules

bacnet.app.handler.error module

**Error Module** This module provides error handlers.

bacnet.app.handler.error.do\_AbortPDU(self, apdu)

This function handles abortions.

Parameters apdu – incoming message

Returns None

 $\verb|bacnet.app.handler.error.do_Error| (self, apdu)$ 

This function handles rejections.

Parameters apdu – incoming message

Returns None

bacnet.app.handler.error.do\_RejectPDU(self, apdu)

This function handles rejections.

Parameters apdu – incoming message

Returns None

bacnet.app.handler.events module

**Event Handler Module** This module provides event handlers.

bacnet.app.handler.events.do\_ConfirmedCOVNotificationRequest (*self*, *apdu*)
This function reads data from request and returns response.

Parameters apdu – incoming message

Returns response

bacnet.app.handler.events.do\_ConfirmedEventNotificationRequest (*self*, *apdu*)

This function reads data from request and returns response.

Parameters apdu – incoming message

Returns None

bacnet.app.handler.events.do\_GetEventInformationRequest(self, apdu)

This function reads data from request and returns response.

Parameters apdu – incoming message

Returns None

```
bacnet.app.handler.events.do_SubscribeCOVPropertyRequest(self, apdu)
```

This function reads data from request and returns response.

Parameters apdu – incoming message

Returns response

bacnet.app.handler.events.do\_SubscribeCOVRequest (self, apdu)

This function reads data from request and returns response.

Parameters apdu – incoming message

**Returns** response

bacnet.app.handler.events.do\_UnconfirmedCOVNotificationRequest(self, apdu)
This function reads data from request.

**Parameters** apdu – incoming message

Returns None

bacnet.app.handler.events.do\_UnconfirmedEventNotificationRequest (self, apdu)
This function reads data from request and returns response.

Parameters apdu – incoming message

Returns None

#### bacnet.app.handler.fileaccess module

**File Access Handler Module** This module provides file access handlers.

bacnet.app.handler.fileaccess.do\_AtomicReadFileRequest(self, apdu)

This function reads data from read file request.

Parameters apdu – incoming message

Returns response

bacnet.app.handler.fileaccess.do\_AtomicWriteFileRequest(self, apdu)

This function reads data from write file request.

**Parameters** apdu – incoming message

**Returns** response

#### bacnet.app.handler.objects module

**Objects Handler Module** This module provides object handlers.

bacnet.app.handler.objects.do\_CreateObjectRequest(self, apdu)

This functions handles object creation.

**Parameters** apdu – incoming message

Returns None

bacnet.app.handler.objects.do\_DeleteObjectRequest(self, apdu)

This functions handles object deletion.

Parameters apdu – incoming message

Returns None

## bacnet.app.handler.simple module

**Application Handler Module** This module provides basic functions for value casting, property creation and general handlers.

bacnet.app.handler.simple.do\_IAmRequest(self, apdu)

This function reads data from I Am request.

Parameters apdu – incoming message

Returns None

bacnet.app.handler.simple.do\_IHaveRequest(self, apdu)

This function reads data from I Have request.

Parameters apdu – incoming message

Returns None

bacnet.app.handler.simple.do\_ReadPropertyMultipleRequest(self, apdu)

This function reads all values from request.

Parameters apdu – incoming message

**Returns** response

bacnet.app.handler.simple.do\_ReadPropertyRequest(self, apdu)

This function reads value from request response.

Parameters apdu – incoming message

Returns None

bacnet.app.handler.simple.do\_WhoHasRequest(self, apdu)

This function responses to WhoHas requests.

Parameters apdu – incoming message

Returns None

bacnet.app.handler.simple.do\_WhoIsRequest(self, apdu)

This function responses to WhoIs requests.

Parameters apdu – incoming message

Returns None

bacnet.app.handler.simple.do\_WritePropertyMultipleRequest(self, apdu)

This function reads all values from request.

Parameters apdu – incoming message

**Returns** response

bacnet.app.handler.simple.do\_WritePropertyRequest(self, apdu)

This function reads value from request response.

**Parameters** apdu – incoming message

Returns None

bacnet.app.handler.simple.property\_to\_result(obj, prop\_id, prop\_index=None)

This function creates an appropriate ReadAccessResultElement.

#### **Parameters**

• obj - object

- prop\_id property id
- prop\_index property array index

Returns ReadAccessResultElement instance

```
bacnet.app.handler.simple.read_property_any(obj, prop_id, prop_index=None, prop=None)
```

This function creates an appropriate property value of type Any.

#### **Parameters**

- obj object
- prop\_id property id
- prop\_index property array index
- **prop** property instance

Returns Any instance

#### Module contents

Application Handler Module This module provides handler for communication callbacks.

```
class bacnet.app.handler.HandlerApplication(*args, **kwargs)
```

Bases: bacpypes.app.Application

This class provides handler functionality for basic requests.

```
add_cov_subscription (apdu, obj, prop=None)
```

This function adds subscription to cov subscription list.

#### **Parameters**

- apdu incoming message
- **obj** object
- prop property

Returns None

## check\_remote\_subscription\_updates(apdu)

This function checks if the cov notification was initiated correctly.

Parameters apdu – incoming message

**Returns** remote subscription exists

```
check_subscription_updates(*args, **kwargs)
```

This function is the actual wrapper of the function call.

```
delete cov subscription (*args, **kwargs)
```

This function is the actual wrapper of the function call.

## delete\_cov\_subscriptions(\*args, \*\*kwargs)

This function is the actual wrapper of the function call.

## do\_AbortPDU (apdu)

This function handles abortions.

Parameters apdu – incoming message

Returns None

#### do\_AtomicReadFileRequest(apdu)

This function reads data from read file request.

Parameters apdu – incoming message

Returns response

#### do\_AtomicWriteFileRequest(apdu)

This function reads data from write file request.

Parameters apdu – incoming message

Returns response

## do\_ConfirmedCOVNotificationRequest(apdu)

This function reads data from request and returns response.

Parameters apdu – incoming message

Returns response

#### do\_CreateObjectRequest (apdu)

This functions handles object creation.

Parameters apdu – incoming message

Returns None

## do\_DeleteObjectRequest(apdu)

This functions handles object deletion.

**Parameters apdu** – incoming message

Returns None

## do\_Error (apdu)

This function handles rejections.

Parameters apdu – incoming message

Returns None

## do\_IAmRequest (apdu)

This function reads data from I Am request.

Parameters apdu – incoming message

Returns None

## do\_IHaveRequest (apdu)

This function reads data from I Have request.

Parameters apdu – incoming message

Returns None

## do\_ReadPropertyMultipleRequest(apdu)

This function reads all values from request.

Parameters apdu – incoming message

Returns response

## do\_ReadPropertyRequest (apdu)

This function reads value from request response.

Parameters apdu – incoming message

#### Returns None

## $do_RejectPDU(apdu)$

This function handles rejections.

Parameters apdu – incoming message

Returns None

#### do\_SubscribeCOVPropertyRequest (apdu)

This function reads data from request and returns response.

Parameters apdu – incoming message

Returns response

## do\_SubscribeCOVRequest (apdu)

This function reads data from request and returns response.

Parameters apdu – incoming message

Returns response

## $do\_UnconfirmedCOVNotificationRequest(apdu)$

This function reads data from request.

Parameters apdu – incoming message

Returns None

## do\_WhoHasRequest (apdu)

This function responses to WhoHas requests.

Parameters apdu – incoming message

Returns None

## do\_WhoIsRequest (apdu)

This function responses to WhoIs requests.

Parameters apdu – incoming message

Returns None

## do\_WritePropertyMultipleRequest(apdu)

This function reads all values from request.

Parameters apdu – incoming message

Returns response

## do\_WritePropertyRequest (apdu)

This function reads value from request response.

Parameters apdu – incoming message

Returns None

#### do\_indication(apdu)

This function initiates appropriate function call for a received request.

Parameters apdu – incoming message

Returns None

## get\_device (address)

This function returns device identifier if known.

Parameters address – device address

**Returns** device identifier

## get\_object\_by\_id(obj\_id)

This function returns object by id.

Parameters obj\_id - object id

Returns object

## get\_object\_by\_name (obj\_name)

This function returns object by name.

Parameters obj\_name - object name

Returns object

## get\_object\_id(obj\_type)

This function provides a unique object id.

Parameters obj\_type - object type

Returns object id

## $handle\_remote\_subscription(apdu)$

This function stores a new remote subscription.

Parameters apdu – outgoing request

**Returns** None

## receive\_remote\_notification(apdu)

This function checks if the cov notification was initiated correctly.

Parameters apdu – incoming message

**Returns** remote subscription exists

## renew\_cov\_subscription(\*args, \*\*kwargs)

This function is the actual wrapper of the function call.

## send\_cov\_notification(subscription, values)

This function transmits cov notifications for subscriptions

#### **Parameters**

- **subscription** subscription
- values sequence of property values

Returns None

bacnet.app.handler.lock\_subscriptions (func=None, block=True, retries=3, sleep=0.05)
This function is a decorator for functions to lock subscriptions during execution.

#### **Parameters**

- func function reference
- block wait until lock is acquired
- retries retry count if not block
- sleep sleep time in secs if not block

**Returns** updated function

```
bacnet.app.handler.restart_on_failure(func=None, retries=3, fail_time=1)
```

This function is a decorator for thread functions to restart after failure :param func: function reference :param retries: restart count within fail time :param fail\_time: time between failures to count retries :return: updated function

#### **Submodules**

## bacnet.app.basic module

#### **Application Basic Module**

This module provides a basic BACpypes application object.

```
class bacnet.app.basic.BasicApplication(*args, **kwargs)
```

Bases: bacnet.app.handler.HandlerApplication, multiprocessing.process.Process

This class describes a basic BACpypes application including simple functionality.

```
add_object (obj)
```

This functions adds an object to the collection.

Parameters obj – object

Returns None

```
check_indication_queue(*args, **kwargs)
```

This function is the actual wrapper of the function call.

```
check_queue (*args, **kwargs)
```

This function is the actual wrapper of the function call.

```
confirmation(*args, **kwargs)
```

This function queues incoming messages.

Parameters apdu - incoming message

Returns None

```
console_interrupt(*args)
```

This function is the catch for interrupts.

Returns None

```
delete\_object(obj)
```

This function removes object from collection.

Parameters obj - object

Returns None

indication (apdu)

This function queues received requests.

Parameters apdu – incoming message

Returns None

iter\_objects()

This function returns an iterator of the object collection.

**Returns** object iterator

```
request (*args, **kwargs)
          This function handles outgoing messages.
              Parameters apdu – outgoing message
              Returns None
     response (*args, **kwargs)
          This function handles outgoing messages as response to a request.
              Parameters apdu – outgoing message
              Returns
     run (*args, **kwargs)
          This function is the actual wrapper of the function call.
     shutdown (*args)
          This function shuts down the process.
              Returns None
     stdout = None
     terminate()
          This function terminates processing.
              Returns None
     update_devices (*args, **kwargs)
          This function is the actual wrapper of the function call.
bacnet.app.basic.poll_hardware(application, obj_tuple)
     This function polls hardware values.
```

## **Parameters**

- application application object
- obj\_tuple object tuples

Returns None

## bacnet.app.define module

## **Application Define Module**

This module contains the user specific definition of a BACpypes Application and Console Commands.

```
class bacnet.app.define.Application(*args, **kwargs)
    Bases: bacnet.app.basic.BasicApplication
```

This class describes the user specific Application functionality including basic builtin functions like "whois" and "iam".

## **Module contents**

#### **Application Module**

This module contains just a single public function for creating a basic device and application to ensure BACnet conform communications by using BACpypes.

**Function for creating device and application:** create\_device\_and\_app(args)

```
bacnet.app.create_app (args, device_init=None, stdout=None, **kwargs)
```

This function creates two BACpypes objects needed for BACnet communications. This includes a local device for identification of the BACnet device and grouping of related BACnet objects as well as an application for message handling from the network.

**Parameters** args – configuration arguments

**Returns** device, application

## 1.1.3 bacnet.console package

## **Subpackages**

bacnet.console.creator package

Submodules

bacnet.console.creator.events module

**Event Handler Module** This module provides COV and event requests.

```
bacnet.console.creator.events.subscribe_request(args, console=None)
```

This function creates a write file stream request.

Usage: subscribe <address> confirmed> <type> <instance> [ <increment> [ <index> ]

## **Parameters**

- **args** list of parameters
- console console object

**Returns** request

## bacnet.console.creator.fileaccess module

File Access Handler Module This module provides file access requests.

```
bacnet.console.creator.fileaccess.rdrec_request(args, console=None)
```

This function creates a read file record request.

Usage: rdrec <address> <instance> <start> <count>

## **Parameters**

- args list of parameters
- console console object

Returns request

```
bacnet.console.creator.fileaccess.rdstr_request(args, console=None)
```

This function creates a read file stream request.

Usage: rdstr <address> <instance> <start> <count>

#### **Parameters**

- args list of parameters
- console console object

## Returns request

bacnet.console.creator.fileaccess.wrrec\_request(args, console=None)

This function creates a write file record request.

Usage: wrrec <address> <instance> <start> <count> ( <data> )\* ...

#### **Parameters**

- args list of parameters
- console console object

## Returns request

bacnet.console.creator.fileaccess.wrstr\_request(args, console=None)

This function creates a write file stream request.

Usage: wrstr <address> <instance> <start> <data>

#### **Parameters**

- **args** list of parameters
- console console object

**Returns** request

#### bacnet.console.creator.local module

**Local Handler Module** This module provides local access requests. - DEPRECATED!

```
bacnet.console.creator.local.local_list(args, i, obj=None, objs=None)
```

This function lists all objects within the application, all properties within an object, or the property value of a property.

## **Parameters**

- **args** list of parameters
- obj object

#### Returns None

bacnet.console.creator.local.local\_set (args, i, obj)

This function sets the property value of a local property.

#### **Parameters**

- args list of parameters
- obj object

#### Returns None

bacnet.console.creator.local.print\_values(values)

This function prints all arguments.

**Parameters** values – list of argument tuples

Returns None

## bacnet.console.creator.objects module

**Objects Handler Module** This module provides object requests.

```
bacnet.console.creator.objects.create_request(args, console=None)
```

This function creates a create object request.

Usage: create <address> <type> [ <vendor> ] ( <property> <value> [ <index> [ priority ] ] )\* ...

## **Parameters**

- args list of parameters
- console console object

## Returns request

bacnet.console.creator.objects.delete\_request(args, console=None)

This function creates a delete object request.

Usage: delete <address> <type> <instance>

#### **Parameters**

- args list of parameters
- console console object

Returns request

## bacnet.console.creator.simple module

**Simple Handler Module** This module contains rudimentary request functions.

```
bacnet.console.creator.simple.cast_value(value, data_type, prop_index=None, prop=None) prop=None)
```

This function casts value to data type.

#### **Parameters**

- value object
- data\_type data type
- prop\_index property array index
- **prop** property instance

Returns casted value

bacnet.console.creator.simple.iam\_request (args, console=None)
This function creates a iam request.

\_

Usage: iam [ <address> ]

#### **Parameters**

- args list of parameters
- console console object

Returns request

```
bacnet.console.creator.simple.ihave_request(args, console=None)
     This function creates a ihave request.
     Usage: ihave [ <address> ] ( <name> | <type> <instance> )
          Parameters
                • args – list of parameters
                • console - console object
          Returns request
bacnet.console.creator.simple.read_request(args, console=None)
     This function creates a read request for multiple objects.
     Usage: read <address> ( <type> <instance> ( <property> [ <index> ] )+ ... )+ ...
          Parameters
                • args – list of parameters
                • console – console object
          Returns request
bacnet.console.creator.simple.whohas_request(args, console=None)
     This function creates a whohas request.
     Usage: whohas [ <address> ] ( <name> | <type> <instance> ) [ <lowlimit> <highlimit> ]
          Parameters
                • args – list of parameters
                • console - console object
          Returns request
bacnet.console.creator.simple.whois_request (args, console=None)
     This function creates a whois request.
     Usage: whois [ <address> ] [ <lowlimit> <highlimit> ]
          Parameters
                • args – list of parameters
                • console – console object
          Returns request
bacnet.console.creator.simple.write request (args, console=None)
     This function creates a write request for multiple objects.
     Usage: write <address> ( <type> <instance> ( <property> <value> [ <index> [ <priority> ] ] )+ ... )+ ...
```

#### **Parameters**

- args list of parameters
- console console object

Returns request

#### **Module contents**

**Console Handler Module** This module provides requests and parser.

```
bacnet.console.creator.request_creator(line, console=None, local_id=1)
This function parses arguments and calls specific command.
```

## Parameters

- line string of command line
- console console object

Returns request object

#### bacnet.console.parser package

#### Submodules

#### bacnet.console.parser.events module

**Event Parser Module** This module provides event parsers.

```
bacnet.console.parser.events.confirmed_cov_notification_request(apdu)
```

This function parses confirmed cov notification request.

Parameters apdu – ConfirmedCOVNotificationRequest

Returns parsed data, output

 $\verb|bacnet.console.parser.events.subscribe_cov_property_request| (apdu)$ 

This function parses subscribe cov property request.

Parameters apdu – SubscribeCOVPropertyRequest

Returns parsed data, output

bacnet.console.parser.events.subscribe\_cov\_request(apdu)

This function parses subscribe cov request.

Parameters apdu – SubscribeCOVRequest

Returns parsed data, output

bacnet.console.parser.events.unconfirmed\_cov\_notification\_request (apdu)

This function parses unconfirmed cov notification request.

Parameters apdu – UnconfirmedCOVNotificationRequest

Returns parsed data, output

#### bacnet.console.parser.fileaccess module

**File Access Parser Module** This module provides file access parsers.

```
bacnet.console.parser.fileaccess.read_file_ack(apdu)
```

This function parses atomic read file acknowledgements.

**Parameters** apdu – AtomicReadFileACK

**Returns** parsed data, output

```
bacnet.console.parser.fileaccess.write_file_ack(apdu)
     This function parses atomic write file acknowledgements.
         Parameters apdu – AtomicWriteFileACK
         Returns parsed data, output
bacnet.console.parser.simple module
Simple Parser Module This module contains rudimentary parser functions.
bacnet.console.parser.simple.iam_request(apdu)
     This function parses i am requests.
         Parameters apdu – IAmRequest
         Returns parsed data, output
bacnet.console.parser.simple.ihave_request(apdu)
     This function parses i have requests.
         Parameters apdu – IHaveRequest
         Returns parsed data, output
bacnet.console.parser.simple.read_property_ack(apdu)
     This function parses read property acknowledgements.
         Parameters apdu – ReadPropertyACK
         Returns parsed data, output
bacnet.console.parser.simple.read_property_multiple_ack(apdu)
     This function parses read property multiple acknowledgements.
         Parameters apdu – ReadPropertyMultipleACK
         Returns parsed data, output
bacnet.console.parser.simple.whohas_request(apdu)
     This function parses who has requests.
         Parameters apdu – WhoHasRequest
         Returns parsed data, output
bacnet.console.parser.simple.whois_request(apdu)
     This function parses who is requests.
         Parameters apdu – WhoIsRequest
```

## **Module contents**

**Acknowledgement Parser Module** This module provides acknowledgement parsing handlers.

Chapter 1. bacnet package

```
bacnet.console.parser.response_parser(apdu, console=None)
This function parses request messages and returns parsed data.
```

#### **Parameters**

• apdu – request message

**Returns** parsed data, output

```
• console – console object
```

Returns parsed data

#### **Submodules**

#### bacnet.console.basic module

#### **Console Basic Module**

```
This module provides a basic BACpypes console commands object.
```

```
class bacnet.console.basic.BasicConsole(device, application, *args, **kwargs)
    Bases: cmd.Cmd, multiprocessing.process.Process
```

This class describes a basic BACpypes shell including simple commands.

```
application = None
```

```
callback (apdu)
```

This function provides a callback for command executions.

Parameters apdu – message

Returns None

#### check\_queue()

This function checks for queued outgoing requests.

Returns None

#### console\_interrupt(\*args)

This function is the catch for interrupts.

Returns None

```
default (line)
```

This function handles the command line if no command was found.

Parameters line - command line

Returns None

device = None

do\_EOF (args)

This function provides an exit.

Usage: EOF

**Parameters** args – string of parameters

Returns None

do\_buggers (args)

This function lists all buggers.

Usage: buggers [ prefix> ]

Parameters args – string of parameters

Returns None

```
do_bugin (args)
     This function activates debugging for mentioned buggers.
     Usage: bugin ( <bugger> )+
         Parameters args – string of parameters
         Returns None
do bugout (args)
     This function deactivates debugging for mentioned buggers.
     Usage: bugout ( <bugger> )+
         Parameters args – string of parameters
         Returns None
do_exit (args)
     This function provides an exit.
     Usage: exit
         Parameters args – string of parameters
         Returns None
do_gc (args)
     This function prints current garbage collection information.
     Usage: gc
         Parameters args – string of parameters
         Returns None
do_info(args)
     This function adjusts package output.
     Usage: info [ (on | off ) (<msg_type>)* ]
         Parameters args – string of parameters
         Returns None
do shell (args)
     This function provides an access to shell execution.
     Usage: ! <command>
         Parameters args – string of parameters
         Returns None
do version (args)
     This function prints current software version.
     Usage: version
         Parameters args – string of parameters
         Returns None
emptyline()
     This function ignores empty lines.
```

Returns None

```
get names()
     This function collects all attributes.
         Returns list of attributes
help_create (text='Usage: create <address> <type> [ <vendor> ] ( <property> <value> [ <index>
                [ priority ] ] )* ...')
help_delete (text='Usage: delete <address> <type> <instance>')
help_iam (text='Usage: iam [ <address> ]')
help ihave (text='Usage: ihave [ <address> ] ( <name> | <type> <instance> )')
help_rdrec (text='Usage: rdrec <address> <instance> <start> <count>')
help_rdstr (text='Usage: rdstr <address> <instance> <start> <count>')
help_read(text='Usage: read <address> ( <type> <instance> (  ( property> [ <index> ] )+ ... )+
             ...')
help_subscribe (text='Usage: subscribe <address> <lifetime> <confirmed> <type> <instance> [
                    cproperty> <increment> [ <index> ] ]')
help whohas (text='Usage: whohas [ <address> ] ( <name> | <type> <instance> ) [ <lowlimit>
                <highlimit> l')
help_whois (text='Usage: whois [ <address> ] [ <lowlimit> <highlimit> ]')
help_write (text='Usage: write <address> ( <type> <instance> ( <property> <value> [ <index> [
               <priority> ] ] )+ ... )+ ...')
help wrrec (text='Usage: wrrec <address> <instance> <start> <count> ( <data> )* ...')
help_wrstr(text='Usage: wrstr <address> <instance> <start> <data>')
onecmd (line, queue=True)
     This function interprets the command line.
         Parameters line – user command line
         Returns command result
postloop()
     This function wraps up readline history after loop has finished.
         Returns None
preloop()
     This function prepares loop by loading readline history file.
         Returns None
print text(text)
     This function prints help text.
         Parameters text - help text
         Returns None
run()
     This function initiates processing.
         Returns None
shutdown (*args)
     This function shuts down the process.
```

1.1. Subpackages 21

Returns None

#### terminate()

This function terminates processing.

Returns None

#### bacnet.console.define module

## **Console Define Module**

This module is an empty shell.

```
class bacnet.console.define.Console(device, application, *args, **kwargs)
Bases: bacnet.console.basic.BasicConsole
```

This Class describes the user specific Console Commands including basic builtin functions like "read" and "write".

#### Module contents

#### **Console Module**

This module contains just a single public function for creating an object for a set of console commands to ensure BACnet conform communications by using BACpypes.

Function for creating console commands: create\_console(application)

```
bacnet.console.create_console(device, application, **kwargs)
```

This function creates a single BACpypes object to support a shell to control BACnet messages.

#### **Parameters**

- device device object
- application application object

Returns console object

## 1.1.4 bacnet.debugging package

## **Submodules**

## bacnet.debugging.log module

## **Debugging Log Module**

This module contains necessary objects to support logging in multiprocessing environments.

```
class bacnet.debugging.log.LoggingFormatter (fmt=None, color=None)
    Bases: logging.Formatter
```

This class is a wrapper for logging formatter to support coloring.

```
format (record)
```

This function formats the message.

Parameters record - logging record

# **Returns** message text class bacnet.debugging.log.MultiProcessingLog(name, mode='a', maxsize=0, backup*count=0*, \*\*kwargs) Bases: logging. Handler This class sends logs to queues. close() This function closes the handler. Returns None emit (record) This function sends the message to queue. Parameters record - message Returns None receive() This function polls for received logs. Returns None

send (record)

This function queues the message.

Parameters record - message

Returns None

setFormatter (fmt)

This function sets the formatter.

**Parameters** fmt – formatter instance

**Returns** 

## **Module contents**

## **Debugging Module**

This module contains basic debugging functionality.

```
bacnet.debugging.ModuleLogger(context=None, details=0, level=None, module_name=None, for-
                                    matter=True)
```

This function creates a general logger.

```
Returns None
```

```
class bacnet.debugging.TimeoutJoinableQueue (*args, **kwargs)
```

Bases: multiprocessing.queues.JoinableQueue

This class is an updated version of JoinableQueue with join timeout.

join (timeout=None)

This function overrides the join function with timeout support.

bacnet.debugging.bacnet\_debug(func=None, formatter=True, level=None)

This function is a decorator for objects to add debugging methods.

#### **Parameters**

• formatter – set formatter string

```
• level – set log level
```

Returns updated object

bacnet.debugging.get\_formatter(color=None)

This function returns a logging formatter instance.

Parameters color - set color

**Returns** logging formatter

bacnet.debugging.get\_loggers(prefix=None)

This function returns the list of all loggers.

**Returns** list of loggers

bacnet.debugging.iso\_now()

This function returns current time in iso format.

**Returns** time in iso format

bacnet.debugging.set\_debug(args=None, stream=None)

This function sets basic logging parameters.

**Parameters** args – arguments

Returns log queue

bacnet.debugging.set\_handler(name, \*\*kwargs)

This function assigns logging handler to certain loggers.

Parameters name - logger name

Returns None

# 1.1.5 bacnet.object package

## **Subpackages**

bacnet.object.basic package

**Submodules** 

bacnet.object.basic.cov\_support module

**COV Support Module** This module contains a list of all objects and properties supporting COV events.

bacnet.object.basic.device module

Object Basic Module This module contains basic definitions of BACpypes Object.

class bacnet.object.basic.device.LocalDeviceObject(\*\*kwargs)

Bases: bacnet.object.basic.general.DeviceObject

This class provides additional functionality for device objects.

defaultProperties = {'numberOfApduRetries': 3, 'maxApduLengthAccepted': 1024, 'apduTimeout': 3000, 'apduSeproperties = [<bacheronic | continue | continue

## bacnet.object.basic.fileaccess module

```
File Access Object Module This module contains File Access Objects.
```

```
class bacnet.object.basic.fileaccess.RecordAccessFileObject(**kwargs)
```

Bases: bacnet.object.basic.general.FileObject

This class provides read/write access to file records.

#### ReadFile (start, count)

This function provides read access.

#### **Parameters**

- start start record
- count record count

## Returns record data

## WriteFile (start, count, data)

This function provides write access.

#### **Parameters**

- start start record
- count record count
- data record data

#### Returns start record

```
class bacnet.object.basic.fileaccess.StreamAccessFileObject(**kwargs)
```

Bases: bacnet.object.basic.general.FileObject

This class provides read/write access to file streams.

## ReadFile (start, count)

This function provides read access.

#### **Parameters**

- **start** start position
- count letter count

## Returns record data

## WriteFile (start, data)

This function provides write access.

## **Parameters**

- start start position
- data data

#### **Returns** start position

## get\_filename()

This function returns the absolute path and file name.

#### Returns file name

#### lock file()

This function locks the file.

**Returns** None

```
unlock file()
          This function unlocks the file.
              Returns None
bacnet.object.basic.general module
Object Basic Module This module contains basic definitions of BACpypes Object.
class bacnet.object.basic.general.AccessCredentialObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes AccessCredentialObject.
     objectType = 'accessCredential'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.AccessDoorObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes AccessDoorObject.
     objectType = 'accessDoor'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.qeneral.AccessPointObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes AccessPointObject.
     objectType = 'accessPoint'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.AccessRightsObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes AccessRightsObject.
     objectType = 'accessRights'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.AccessUserObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes AccessUserObject.
     objectType = 'accessUser'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.AccessZoneObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes AccessZoneObject.
     objectType = 'accessZone'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
```

```
class bacnet.object.basic.general.AccumulatorObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes AccumulatorObject.
     objectType = 'accumulator'
     properties = [<bacher.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacher.object.properties.Reada
class bacnet.object.basic.general.AnalogInputObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes AnalogInputObject.
     objectType = 'analogInput'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.AnalogOutputObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes AnalogOutputObject.
     objectType = 'analogOutput'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.AnalogValueObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes AnalogValueObject.
     objectType = 'analogValue'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.AveragingObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes AveragingObject.
     objectType = 'averaging'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.BinaryInputObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes BinaryInputObject.
     objectType = 'binaryInput'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.BinaryOutputObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes BinaryOutputObject.
     objectType = 'binaryOutput'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.BinaryValueObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes Binary Value Object.
     objectType = 'binaryValue'
```

```
properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.BitStringValueObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes BitStringValueObject.
     objectType = 'bitstringValue'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.CalendarObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes CalendarObject.
     objectType = 'calendar'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.CharacterStringValueObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes CharacterStringValueObject.
     objectType = 'characterstringValue'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.CommandObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes CommandObject.
     objectType = 'command'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.CredentialDataInputObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes CredentialDataInputObject.
     objectType = 'credentialDataInput'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.DatePatternValueObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes DatePatternValueObject.
     objectType = 'datePatternValue'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.DateTimePatternValueObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes DateTimePatternValueObject.
     objectType = 'datetimePatternValue'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.DateTimeValueObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes DateTimeValueObject.
```

```
objectType = 'datetimeValue'
     properties = [<bacnet.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacnet.object.properties.Reada
class bacnet.object.basic.general.DateValueObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes DateValueObject.
     objectType = 'dateValue'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.DeviceObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes DeviceObject.
     objectType = 'device'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.EventEnrollmentObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes EventEnrollmentObject.
     objectType = 'eventEnrollment'
     properties = [<bacher.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacher.object.properties.Reada
class bacnet.object.basic.general.EventLogObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes EventLogObject.
     objectType = 'eventLog'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.FileObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes FileObject.
     objectType = 'file'
     properties = [<bacher.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacher.object.properties.Reada
class bacnet.object.basic.general.GlobalGroupObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes GlobalGroupObject.
     objectType = 'globalGroup'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.GroupObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes GroupObject.
     objectType = 'group'
     properties = [<bacher.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacher.object.properties.Reada
```

class bacnet.object.basic.general.IntegerValueObject(\*\*kwargs)

```
Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes IntegerValueObject.
     objectType = 'integerValue'
     properties = [<bacher.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacher.object.properties.Reada
class bacnet.object.basic.general.LargeAnalogValueObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes LargeAnalogValueObject.
     objectType = 'largeAnalogValue'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.LifeSafetyPointObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes LifeSafetyPointObject.
     objectType = 'lifeSafetyPoint'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.LifeSafetyZoneObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes LifeSafetyZoneObject.
     objectType = 'lifeSafetyZone'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.LoadControlObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes LoadControlObject.
     objectType = 'loadControl'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.LoopObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes LoopObject.
     objectType = 'loop'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.MultiStateInputObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes MultiStateInputObject.
     objectType = 'multiStateInput'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.MultiStateOutputObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes MultiStateOutputObject.
     objectType = 'multiStateOutput'
```

```
properties = [<backers.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <backers.Reada
class backers.object.basic.general.MultiStateValueObject (**kwargs)
    Bases: backers.object.basic.general.Object
    This class is an covextended version of backypes MultiStateValueObject.
    objectType = 'multiStateValue'
    properties = [<backers.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <backers.object.properties.Reada</pre>
```

class bacnet.object.basic.general.NetworkSecurityObject(\*\*kwargs)

Bases: bacnet.object.basic.general.Object

This class is an cov extended version of bacpypes NetworkSecurityObject.

objectType = 'networkSecurity'

properties = [<bacnet.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacnet.object.properties.Reada

class bacnet.object.basic.general.NotificationClassObject(\*\*kwargs)

Bases: bacnet.object.basic.general.Object

This class is an cov extended version of bacpypes NotificationClassObject.

objectType = 'notificationClass'

properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada

```
class bacnet.object.basic.general.Object (**kwargs)
    Bases: bacpypes.object.Object
```

This class is an extension of the bacpypes Object class to support COV notifications.

ReadProperty (propid, arrayIndex=None, \*\*kwargs)

This function handles reading of property values.

#### **Parameters**

- propid property identifier
- arrayIndex property index

**Returns** property value

**WriteProperty** (propid, value, arrayIndex=None, priority=None, direct=False, \*\*kwargs)
This function handles writing of property values.

#### **Parameters**

- propid property identifier
- value property value
- arrayIndex property index
- **priority** write priority
- direct direct write

Returns property value

## add\_cov\_subscription (subscription)

This function adds subscription to cov subscription list.

**Parameters** subscription – subscription

Returns None

```
cov_supported(prop=None)
```

This function checks if COV subscription is supported.

Parameters prop – property object or identifier

**Returns** COV is supported

## delete\_cov\_subscription (subscriptions, inform\_app=False)

This function deletes subscription from cov subscription list.

#### **Parameters**

- subscriptions subscriptions
- inform\_app inform application

Returns None

## get\_property (identifier)

This function returns the property for identifier: :param identifier: property identifier :return: property

## get\_value (identifier)

This function returns the value for property identifier: param identifier: property identifier :return: value

#### poll\_hardware()

This function checks for value updates for hardware.

Returns None

```
renew cov subscription (subscription)
```

This function checks if subscription can be renewed and returns boolean of this action.

Parameters subscription - subscription

Returns subscription renewed

## set\_application (application)

This function defines the application associated to this object.

Parameters application – application object

**Returns** None

## set\_value (identifier, value)

This function sets the value for property identifier. :param identifier: property identifier :param value: property value :return: None

class bacnet.object.basic.general.OctetStringValueObject(\*\*kwargs)

Bases: bacnet.object.basic.general.Object

This class is an cov extended version of bacpypes OctetStringValueObject.

```
objectType = 'octetstringValue'
```

properties = [<bacher.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacher.object.properties.Reada

```
class bacnet.object.basic.general.PositiveIntegerValueObject(**kwargs)
```

Bases: bacnet.object.basic.general.Object

This class is an cov extended version of bacpypes PositiveIntegerValueObject.

objectType = 'positiveIntegerValue'

properties = [<bacher.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacher.object.properties.Reada

```
class bacnet.object.basic.general.ProgramObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes ProgramObject.
     objectType = 'program'
     properties = [<bacher.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacher.object.properties.Reada
class bacnet.object.basic.general.PulseConverterObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes PulseConverterObject.
     objectType = 'pulseConverter'
     properties = [<bacher.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacher.object.properties.Reada
class bacnet.object.basic.general.ScheduleObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes ScheduleObject.
     objectType = 'schedule'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.StructuredViewObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes StructuredViewObject.
     objectType = 'structuredView'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.TimePatternValueObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes TimePatternValueObject.
     objectType = 'timePatternValue'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.TimeValueObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes TimeValueObject.
     objectType = 'timeValue'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.TrendLogMultipleObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes TrendLogMultipleObject.
     objectType = 'trendLogMultiple'
     properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada
class bacnet.object.basic.general.TrendLogObject(**kwargs)
     Bases: bacnet.object.basic.general.Object
     This class is an cov extended version of bacpypes TrendLogObject.
     objectType = 'trendLog'
```

## properties = [<bacret.object.properties.ObjectIdentifierProperty 'objectIdentifier'>, <bacret.object.properties.Reada

```
bacnet.object.basic.general.cls_obj
alias of Object
```

bacnet.object.basic.general.get\_datatype(cls, prop\_id, vendor\_id=0)

This function returns the data type for a specified class and property identifier.

#### **Parameters**

- cls object class
- prop\_id property identifier

## Returns object type

bacnet.object.basic.general.get\_object\_class(cls, vendor\_id=0)

This function returns the object type for a specified class.

Parameters cls - object class

Returns object type

bacnet.object.basic.general.new\_class
alias of TrendLogMultipleObject

bacnet.object.basic.general.new\_property(cls\_type, old\_prop)

This function converts bacpypes properties into new bacnet properties.

#### **Parameters**

- cls\_type object type
- old\_prop old property

## Returns new property

bacnet.object.basic.general.register\_object\_type (cls, vendor\_id=0)
This function stores new object types.

Parameters cls - object class

Returns None

## bacnet.object.basic.program module

Object Basic Module This module contains basic definitions of BACpypes Object.

```
class bacnet.object.basic.program.ExecProgramObject (**kwargs)
    Bases: bacnet.object.basic.general.ProgramObject
```

This class provides additional functionality for python programs.

**WriteProperty** (*prop\_id*, *value*, *arrayIndex=None*, *priority=None*, *direct=False*) This function writes to property.

#### **Parameters**

- prop\_id property identifier
- value value
- arrayIndex index
- priority priority

#### • direct - direct

Returns None

## do\_haltProgram()

This functions watches over the halt process of the executed program.

Returns None

#### haltProgram()

This function halts the program.

Returns None

#### loadProgram()

This function loads the program.

Returns None

#### runProgram()

This function runs the program.

**Returns** None

#### safe\_delete()

This function handles safe deletion

Returns None

### set\_application (application)

This function defines the application associated to this object.

Parameters application – application object

Returns None

### unloadProgram()

This function unloads the program.

Returns None

## watchdog(\*funcs)

This function watches over the executed program changes.

Returns None

**Module contents** 

Object Basic Module This module contains basic definitions of BACpypes Object.

bacnet.object.hardware package

Subpackages

bacnet.object.hardware.terra package

**Submodules** 

bacnet.object.hardware.terra.ablib\_dummy module

```
Terra_Board ABLIB_Dummy Module This module contains dummy classes for hardware abstraction.
class bacnet.object.hardware.terra.ablib_dummy (*args, **kwargs)
     Bases: object
     This class is a generic dummy class.
     identifier = None
     name = "
class bacnet.object.hardware.terra.ablib_dummy.BinaryReadDummy(*args, **kwargs)
     Bases: bacnet.object.hardware.terra.ablib_dummy.ABLIB_Dummy
     This class is a dummy for reading binary values.
     get (identifier=None)
         This function is a dummy for getting the led status.
     value = False
class bacnet.object.hardware.terra.ablib_dummy.BinaryWriteDummy (*args, **kwargs)
     Bases: bacnet.object.hardware.terra.ablib dummy.BinaryReadDummy
     This class is a dummy for reading and writing binary values
     off (identifier=None)
         This function is a dummy for turning off the led.
     on (identifier=None)
         This function is a dummy for turning on the led.
class bacnet.object.hardware.terra.ablib_dummy.Daisy11(connector_id, led_id)
     Bases: bacnet.object.hardware.terra.ablib_dummy.BinaryWriteDummy
     This class is a dummy for the terra board's led array.
     name = 'LED'
class bacnet.object.hardware.terra.ablib_dummy.Daisy19(connector_id, position, out-
     Bases: bacnet.object.hardware.terra.ablib_dummy.BinaryWriteDummy
     This class is a dummy for the terra board's 4 channel output switch.
     name = 'Output'
class bacnet.object.hardware.terra.ablib dummy.Daisy20(*args, **kwargs)
     Bases: bacnet.object.hardware.terra.ablib_dummy.BinaryReadDummy
     This class is a dummy for the terra board's adc.
     convert (value)
         This function is a dummy to convert the bit value into voltage.
             Parameters value – bit value
             Returns voltage
     name = 'ADC'
class bacnet.object.hardware.terra.ablib dummy.Daisy22(*args, **kwargs)
     Bases: bacnet.object.hardware.terra.ablib dummy.BinaryWriteDummy
     This class is a dummy for the terra board's backlight led of the lcd display.
     name = 'Backlight LED'
```

```
class bacnet.object.hardware.terra.ablib_dummy.Daisy24(*args, **kwargs)
     Bases: bacnet.object.hardware.terra.ablib_dummy.ABLIB_Dummy
     This class is a dummy for the terra board's lcd display and button array.
     backled = <bachet.object.hardware.terra.ablib_dummy.Daisy22 'Backlight LED None'>
     name = 'LCD'
     pressed (keyid)
          This function is a dummy for checking pressed buttons.
              Parameters keyid - button id
              Returns button pressed
     putstring(value)
          This function is a dummy for putting a string to the LCD display.
              Parameters value - string
              Returns None
     setcurpos(x, y)
          This function is a dummy for setting the cursor on the LCD display.
              Parameters
                   • \mathbf{x} - \mathbf{x} position
                   • y - y position
              Returns None
Module contents
Terra Module This module contains Terra Board specific objects.
class bacnet.object.hardware.terra.AbstractDaisy20 (identifier)
     Bases: object
     This class is an abstraction of the ablib.Daisy20 class.
     get()
          This function is a wrapper for the get function.
              Returns voltage
     identifier = None
class bacnet.object.hardware.terra.AbstractDaisy24Backlight(identifier=None)
     Bases: object
     This class is an abstraction for backlight of the ablib.Daisy24 class.
     get()
          This function is a wrapper for the backled.get function.
              Returns led on/off
     off()
          This function is a wrapper for the backled.off function.
              Returns None
```

```
on ()
          This function is a wrapper for the backled.on function.
              Returns None
class bacnet.object.hardware.terra.AbstractDaisy24Button(identifier)
     Bases: object
     This class is an abstraction for buttons of the ablib.Daisy24 class.
     get()
          This function is a wrapper for the pressed function.
              Returns button pressed
     identifier = None
class bacnet.object.hardware.terra.AbstractDaisy24LCD (identifier=None)
     Bases: object
     This class is an abstraction for lcd of the ablib.Daisy24 class.
          This function is a providing a value buffer.
              Returns button pressed/not pressed
     identifier = None
     value = "
     write(value)
          This function is a wrapper for the putstring and setcurpos function
              Returns None
class bacnet.object.hardware.terra.New_Daisy20 (max_voltage=10, bits=10)
     Bases: object
     DAISY-20 (ADC module)
     adc_path = '/sys/bus/iio/devices/iio:device0/'
     chan_file = 'in_voltage%i_raw'
     convert (bit_value)
     get(ch=0)
     max_voltage = 0
     volt_per_point = 0
Module contents
Objects Hardware Module This module collects objects and classes with hardware specific properties.
bacnet.object.hardware.discover_hardware_objects()
     This function registers all defined objects in all hardware modules.
          Returns object dictionary
```

#### **Submodules**

### bacnet.object.define module

#### **Object Define Module**

This module contains user specific definitions of BACpypes Object and a list to collect all builtin Objects needed.

```
bacnet.object.define.get_initial_object_list()
```

This function creates the object list.

Returns object list

### bacnet.object.primitivedata module

#### **Primitive Data Module**

This module contains improved bacpypes primitive data classes.

```
class bacnet.object.primitivedata.COVSubscription(*args, **kwargs)
```

Bases: bacpypes.basetypes.COVSubscription

This class has specific updates.

sequenceElements = [<backgraphes.constructeddata.Element instance at 0x10586f0e0>, <backgraphes.constructeddata.Element

```
class bacnet.object.primitivedata.ObjectPropertyReference(*args, **kwargs)
```

Bases: bacpypes.constructeddata.Sequence

This class has an extension to support instances without property identifier.

 ${\tt sequenceE1ements} = [< bacpypes.constructed data. Element instance at 0x10586f1b8>, < backproprint instance at 0x10586f1b8>, < back$ 

```
class bacnet.object.primitivedata.Remaining(time)
```

Bases: bacpypes.primitivedata.CharacterString

This class is an extended version of Unsigned.

#### decode (tag)

This function decodes the value from network transmission.

Parameters tag – Tag

Returns None

## encode(tag)

This function encodes the value for network transmission.

Parameters tag – Tag

Returns None

#### remaining\_time

This function calculates the remaining time till defined datetime

**Returns** remaining time in seconds

```
class bacnet.object.primitivedata.RingDict(size, *args, **kwargs)
```

Bases: collections.OrderedDict

This class is a dictionary ring buffer without overriding protection.

#### size

This function returns the size of the ring buffer.

#### **Returns** buffer size

```
{\bf class} \ {\tt bacnet.object.primitive data.RingList} \ ({\it size}, {\it seq=()})
```

Bases: list

This class is a ring buffer without overriding protection.

#### append (data)

This function adds data to ring buffer.

Parameters data - data to be added

**Returns** None

#### first value()

This function returns the value last appended.

Returns last value

#### last value()

This function returns the value last appended.

Returns last value

#### size

This function returns the size of the ring buffer.

**Returns** buffer size

```
class bacnet.object.primitivedata.Unsigned(*args)
```

Bases: bacpypes.primitivedata.Unsigned, long

This class has an integer extension to support builtin functions like div float.

## bacnet.object.properties module

#### **Object Properties Module**

This module contains specific properties for the usage within objects. Especially it provides updated property COV functionality for bacpypes objects.

```
\textbf{class} \texttt{ bacnet.object.properties.ActiveCovSubscriptionsProperty} \ (*args, **kwargs)
```

Bases: bacnet.object.properties.ReadableProperty

This class is an extension of the ReadableProperty class for active cov subscriptions.

 $\textbf{ReadProperty} \ (obj, arrayIndex=None, dictionary=False)$ 

This function handles reading.

#### **Parameters**

- obj property
- arrayIndex index

Returns property value

WriteProperty (obj, value, arrayIndex=None, priority=None, direct=False)

This function handles writing.

#### **Parameters**

- **obj** property
- value property value
- arrayIndex index
- priority priority
- direct direct

#### Returns property value

class bacnet.object.properties.CurrentDateProperty (identifier)

Bases: bacnet.object.properties.OptionalProperty

This class is an extension of the Optional Property class for current date.

#### ReadProperty (obj, arrayIndex=None)

This function handles reading.

#### **Parameters**

- **obj** property
- arrayIndex index

Returns property value

WriteProperty (obj, value, arrayIndex=None, priority=None, direct=False)

This function handles writing.

#### **Parameters**

- **obj** property
- value property value
- arrayIndex index
- priority priority
- direct direct

#### Returns property value

class bacnet.object.properties.CurrentTimeProperty(identifier)

Bases: bacnet.object.properties.OptionalProperty

This class is an extension of the OptionalProperty class for current time.

## ReadProperty (obj, arrayIndex=None)

This function handles reading.

#### **Parameters**

- obj property
- arrayIndex index

Returns property value

**WriteProperty** (*obj*, *value*, *arrayIndex=None*, *priority=None*, *direct=False*)
This function handles writing.

### **Parameters**

- **obj** property
- value property value

```
• arrayIndex - index
```

- priority priority
- direct direct

Returns property value

class bacnet.object.properties.HardwareAccessObject (hw\_object, write=False, hysteresis=False, buffer\_size=0)

Bases: object

This class is a wrapper for terra hardware objects.

get (index=None)

This function is a wrapper for getting the actual hardware value

Parameters index – array index

Returns value

hardware = None

hysteresis (value)

This function applies a user specific hysteresis to the value.

Parameters value – hardware value

Returns updated value

set (value, data\_type, index=None)

This function converts the

#### **Parameters**

- value value
- data\_type data type
- index array index

Returns value

writable = False

Bases: bacnet.object.properties.ReadableProperty

This class is an extension of the ReadableProperty class for object identifiers.

**WriteProperty** (*obj*, *value*, *arrayIndex=None*, *priority=None*, *direct=False*) This function handles writing.

## **Parameters**

- **obj** property
- value property value
- arrayIndex index
- **priority** priority
- direct direct

Returns property value

```
class bacnet.object.properties.OptionalProperty (identifier,
                                                                        datatype,
                                                                                    default=None,
                                                                                   mutable=False.
                                                           optional=True.
                                                           cov support=False)
     Bases: bacnet.object.properties.StandardProperty
     This class is an extension of the bacpypes Optional Property class to support COV notifications.
class bacnet.object.properties.Property (identifier, datatype, **kwargs)
     Bases: object
     This class is an extension of the bacpypes Property class to support COV notifications.
     ReadProperty (obj, arrayIndex=None)
          This function handles reading.
              Parameters
                  • obj – property
                  • arrayIndex - index
              Returns property value
     WriteProperty (obj, value, arrayIndex=None, priority=None, direct=False)
          This function handles writing.
              Parameters
                  • obj – property
                  • value - property value
                  • arrayIndex - index
                  • priority – priority
                  • direct - direct
              Returns property value
class bacnet.object.properties.ReadableProperty(identifier,
                                                                        datatype,
                                                                                    default=None,
                                                           optional=False.
                                                                                   mutable=False.
                                                           cov_support=False)
     Bases: bacnet.object.properties.StandardProperty
     This class is an extension of the bacpypes ReadableProperty class to support COV notifications.
class bacnet.object.properties.StandardProperty(*args, **kwargs)
     Bases: bacnet.object.properties.Property
     This class is an extension of the bacpypes StandardProperty class to support COV notifications.
class bacnet.object.properties.WritableProperty (identifier,
                                                                        datatype,
                                                                                    default=None,
                                                           optional=False,
                                                                                   mutable=True.
```

#### **Module contents**

#### **Objects Module**

This module contains just a single function to collect all user specific bacpypes Objects.

Bases: bacnet.object.properties.StandardProperty

1.1. Subpackages 43

This class is an extension of the bacpypes WritableProperty class to support COV notifications.

cov\_support=False)

```
bacnet.object.get_object_list()
```

This function collects all defined user specific and relevant builtin bacpypes Objects.

**Parameters** examples – enable example objects

Returns object\_list

## 1.1.6 bacnet.sandbox package

## **Subpackages**

#### **Submodules**

#### bacnet.sandbox.interface module

#### Sandbox Interface Module

This module contains the Transformation Implementation for the Sandbox interface. It is simply copied from the PyPy code and thereby not commented.

```
\verb|bacnet.sandbox.interface.read_message| (\textit{timeout=None})
```

```
bacnet.sandbox.interface.receive()
```

This function is waiting for arriving messages via an event.

#### Returns message

```
bacnet.sandbox.interface.transmit(line)
```

This function is transmitting outgoing messages.

#### Returns None

```
bacnet.sandbox.interface.write_message(*x)
```

## bacnet.sandbox.process module

#### Module contents

#### **Sandbox Module**

This module contains handlers for the pypy sandbox environment.

```
bacnet.sandbox.get_platform_name()
```

This function returns the platform name.

**Returns** platform name

```
bacnet.sandbox.get_sandbox_process(executable)
```

This function returns a sandbox process object.

**Parameters** executable – relative path to untrusted executable

Returns sandbox process

```
bacnet.sandbox.sandbox_interact(sandbox_process)
```

This function interacts with the sandbox process.

Parameters sandbox\_process – sandbox process object

## Returns None

```
bacnet.sandbox.sandbox_support(platform_name='darwin-x86_64')
```

This function checks if compiled sandbox version of pypy exists for this system.

**Returns** sandbox is supported on this system

## 1.1.7 bacnet.system package

## **Subpackages**

bacnet.system.config package

Submodules

bacnet.system.config.helper module

**Handler Helper Module** This module provides access to local interface addresses.

```
\verb|bacnet.system.config.helper.get_local_ip| (interface)
```

This function retrieves an IP address from the defined interface.

Parameters interface – network interface for IP address retrieval

Returns ip\_address

## bacnet.system.config.parser module

**Config Parser Module** This module provides an extended version of the BCApypes argument parser.

This class combines BACpypes builtin config and parameter parser with customized parameters.

```
arg_object = None
```

```
parse_args (*args, **kwargs)
```

This function wraps the parse\_args of ConfigArgumentParser to intercept version requests.

Returns self

update()

This function updates the argument object.

**Returns** parsed parameters

#### Module contents

```
BACnet Config Module This module provides configuration functionality.
class bacnet.system.config.ConfigManager(**kwargs)
     Bases: object
     This class handles the configuration requests by the user.
     data = \{\}
     filename = 'BACnet.ini'
     get (key)
          This function retrieves specified value provided by the user.
               Parameters key – value to retrieve
               Returns None
     get_input (key, prompt)
          This function handles user input.
               Parameters
                   • key - default key
                   • prompt - prompt text
               Returns user response
     start()
          This function initiates the user interface.
               Returns None
     store()
          This function stores the retrieved data.
               Returns None
     valid(key, response)
          This function checks, if response is valid
               Parameters
                   • key – value to retrieve
                   • response – retrieved value
               Returns
     verify_address (key='address', response='', interface=True)
          This function retrieves an ip address provided by the user.
               Parameters response - user input
               Returns verified response
     verify_bbmd(response)
          This function verifies an ip address provided by the user.
               Parameters response – user input
               Returns verified response
```

## **Submodules**

## bacnet.system.managing module

#### **BACnet Managing Module**

This module provides managing tools for multiprocessing.

```
bacnet.system.managing.client_manager(address=None, authkey=None)
```

This function creates a client manager

#### Returns manager

```
bacnet.system.managing.server_manager(log_queue, ip_address, port, console=False, we-
bgui=False)
```

This function creates a server manager.

Returns manager, server

## bacnet.system.vendors module

#### **Vendors**

This module provides an updater for BACnet vendor IDs.

```
class bacnet.system.vendors.TableParser
```

Bases: htmllib.HTMLParser

This class implements a table parser for the BACnet vendor list.

#### end\_tr()

This function handles the end of a column.

#### Returns

## ${\tt handle\_data}\,(data)$

This function handles tag data.

Parameters data - tag data

Returns None

## handle\_starttag(tag, method, attrs)

This function is called on every start tag.

#### **Parameters**

- tag full tag
- method tag function
- attrs tag attributes

Returns None

#### handle\_td(data)

This function handles a new column.

Parameters data – tag content

Returns None

```
start td(attrs)
```

This function handles a new column.

Parameters attrs - tag attributes

Returns None

```
bacnet.system.vendors.get vendors()
```

This function requests the current vendor list and returns a parsed dictionary

**Returns** vendor dictionary

### bacnet.system.version module

#### **BACnet System Version Module**

This module handles version printing and normalizing according to PEP 386.

```
bacnet.system.version.create_version(version)
```

This function is a verlib wrapper to create necessary version and git information.

Parameters version – get current version tuple

Returns full\_version, git\_info

```
bacnet.system.version.get_version()
```

This function returns current version string and exits program.

Returns None

#### **Module contents**

## **BACnet System Module**

This module contains the bacnet system class.

```
 \textbf{class} \ \texttt{bacnet.system.BACnetSystem} \ (\textit{stdin} = <\textit{open file '} <\textit{stdin} >\textit{'}, \ \textit{mode 'r'} >\textit{, stdout} = <\textit{open file '} <\textit{stdout} <\textit{open file '} <\textit{stderr} >\textit{'}, \ \textit{mode 'w'} >\textit{, stderr} = <\textit{open file '} <\textit{stderr} >\textit{'}, \ \textit{mode 'w'} >\textit{)}
```

Bases: object

This class handles the BACnet system.

```
application = None
```

console = None

```
console_interrupt(*args)
```

This function is the catch for interrupts.

Returns None

```
do_buggers (config_args)
```

This function lists all buggers.

**Parameters** config\_args – configuration arguments

Returns None

```
do_config(config_args)
```

This function sets configuration parameters.

**Parameters** config\_args – configuration arguments

```
Returns None
do_hardware (config_args)
     This function lists all creatable hardware objects.
         Parameters config_args – configuration arguments
         Returns None
do_set_tag(config_args)
     This function initiates the BACnet system start up as shell.
         Parameters config_args – configuration arguments
         Returns None
do_shell (config_args)
     This function initiates the BACnet system start up as shell.
         Parameters config_args - configuration arguments
         Returns None
do_start (config_args, console=False, webgui=False)
     This function initiates the BACnet system start up as reactive application.
         Parameters config_args – configuration arguments
         Returns None
do_webgui (config_args)
    This function initiates the BACnet system start up as web gui.
         Parameters config_args - configuration arguments
         Returns None
exit (code=0)
     This function exits the system.
         Parameters code - exit code
         Returns None
manager = None
shutdown (*args)
     This function shuts down the process.
```

## 1.1.8 bacnet.webgui package

Returns None

## **Subpackages**

bacnet.webgui.caching package

stderr = None
stdin = None
stdout = None

**Subpackages** 

| bacnet.webgui.caching.base package   |
|--|
| Submodules   |
| bacnet.webgui.caching.base.filter module   |
| bacnet.webgui.caching.base.helpers module  |
| bacnet.webgui.caching.base.options module  |
| bacnet.webgui.caching.base.relations module  |
| Module contents  |
| Submodules   |
| bacnet.webgui.caching.cache module   |
| Module contents  |
| bacnet.webgui.control package  |
| Subpackages  |
| bacnet.webgui.control.templatetags package   |
| Submodules   |
| bacnet.webgui.control.templatetags.menu module   |
| Menu Templatetags Module This module contains important descriptions for the menu.   |
| bacnet.webgui.control.templatetags.menu.url_attr(context, label, attribute, exact=False, **kwargs)  This function marks links depending on the request's path. |
| Module contents  |
| Control Templatetags Module This module is a collection of all tags used within the app's templates.   |
| bacnet.webgui.control.views package  |
| Submodules   |

### bacnet.webgui.control.views.access module

### bacnet.webgui.control.views.devices module

#### Module contents

**Views Module** This module contains all descriptions of web access interfaces.

```
bacnet.webgui.control.views.breadcrumbs(path)
```

This function provides the breadcrumbs for a path.

Parameters path - path

**Returns** list of breadcrumbs

bacnet.webgui.control.views.control\_views\_render(request, template\_file, arg\_dict={}}, local=True)

This function provides general rendering for all templates.

#### **Parameters**

- request Django request
- template\_file template filename
- arg\_dict arguments
- local is local template

**Returns** HTTP response

 $\verb|bacnet.webgui.control.views.get_crumb_name| (link)$ 

This function provides the breadcrumb name for a link

Parameters link - link

Returns breadcrumb name

bacnet.webgui.control.views.index(request)

This function provides the index page of the project.

Parameters request - Django request

Returns HTTP response

## **Submodules**

bacnet.webgui.control.models module

bacnet.webgui.control.urls module

**Control URL Module** This module contains the description of all app based pages on the web interface.

**Module contents** 

**Control Module** This module contains all necessary descriptions for the web interface and internal structure.

bacnet.webgui.webgui package

Subpackages

bacnet.webgui.webgui.settings package

**Submodules** 

bacnet.webgui.webgui.settings.apps module

**App Settings Module** This module contains app specific definitions for Django settings.

bacnet.webgui.webgui.settings.private module

**Private Settings Module** This module contains private definitions for Django settings.

For more information on this file, see https://docs.djangoproject.com/en/1.7/topics/settings/

For the full list of settings and their values, see https://docs.djangoproject.com/en/1.7/ref/settings/

**Submodules** 

bacnet.webgui.webgui.urls module

bacnet.webgui.wsgi module WSGI config for webgui project.

It exposes the WSGI callable as a module-level variable named application.

For more information on this file, see https://docs.djangoproject.com/en/1.7/howto/deployment/wsgi/

**Module contents** 

**Submodules** 

bacnet.webgui.bacnet access module

**BACnet Access Module** 

This module provides access to the inter-process communication of the system.

bacnet.webgui.bacnet\_access.api\_create(line)

This function wraps the API method create.

Parameters line - command

Returns APDU object

```
bacnet.webgui.bacnet_access.api_receive()
```

This function wraps the API methods receive and parse.

### Returns parsed APDU object

```
bacnet.webgui.bacnet_access.api_transmit(line=None, request=None)
```

This function wraps the API methods create and send.

#### **Parameters**

- line command
- request APDU object

Returns sending successful

## bacnet.webgui.manage module

#### Manage Module

This module manages the django environment and process start up.

#### **Module contents**

#### **BACnet WebGUI Module**

This module contains a django project for BACnet interaction.

```
class bacnet.webqui.DjangoProcess (address, port)
```

Bases: multiprocessing.process.Process

This class handles the django process.

#### receiver()

This function provides the environment for the receiver thread.

#### Returns None

run()

This function is executed as a separate process.

```
shutdown (*args)
```

This function shuts down the process.

Returns None

bacnet.webgui.create\_webgui(address, port)

This function creates a django subprocess.

Returns webgui process

## 1.2 Submodules

## 1.3 bacnet.settings module

## 1.3.1 BACnet Settings Module

This module contains general settings for the BACnet system.

## 1.4 Module contents

## 1.4.1 BACnet Framework

This module contains wrappers for BACpypes to ensure seamless integration of BACnet functionality to user specific use cases.

## **CHAPTER**

# TWO

# **INDICES AND TABLES**

- genindex
- modindex
- search

#### PYTHON MODULE INDEX

```
h
                                          bacnet.sandbox.interface, 44
                                          bacnet.settings.54
bacnet.54
                                          bacnet.system, 48
bacnet.api, 3
                                          bacnet.system.config, 45
bacnet.app, 12
                                          bacnet.system.config.helper,45
bacnet.app.basic, 11
                                          bacnet.system.config.parser,45
bacnet.app.define, 12
                                          bacnet.system.managing,47
bacnet.app.handler,7
                                          bacnet.system.vendors, 47
bacnet.app.handler.error, 4
                                          bacnet.system.version, 48
bacnet.app.handler.events,4
                                          bacnet.webgui, 53
bacnet.app.handler.fileaccess, 5
                                          bacnet.webgui.bacnet_access,52
bacnet.app.handler.objects,5
                                          bacnet.webgui.control,51
bacnet.app.handler.simple, 6
                                          bacnet.webgui.control.templatetags, 50
bacnet.console, 22
                                          bacnet.webgui.control.templatetags.menu,
bacnet.console.basic, 19
                                                 50
bacnet.console.creator, 16
                                          bacnet.webgui.control.urls,51
bacnet.console.creator.events, 13
                                          bacnet.webqui.control.views, 51
bacnet.console.creator.fileaccess.13
                                          bacnet.webgui.manage, 53
bacnet.console.creator.local, 14
                                          bacnet.webqui.webqui,52
bacnet.console.creator.objects, 15
                                          bacnet.webqui.webqui.settings,52
bacnet.console.creator.simple, 15
                                          bacnet.webqui.webqui.settings.apps, 52
bacnet.console.define, 22
                                          bacnet.webgui.webgui.settings.private,
bacnet.console.parser, 18
bacnet.console.parser.events, 17
                                          bacnet.webgui.webgui.wsgi,52
bacnet.console.parser.fileaccess, 17
bacnet.console.parser.simple, 18
bacnet.debugging, 23
bacnet.debugging.log, 22
bacnet.object, 43
bacnet.object.basic, 35
bacnet.object.basic.cov_support, 24
bacnet.object.basic.device, 24
bacnet.object.basic.fileaccess, 25
bacnet.object.basic.general, 26
bacnet.object.basic.program, 34
bacnet.object.define, 39
bacnet.object.hardware, 38
bacnet.object.hardware.terra, 37
bacnet.object.hardware.terra.ablib_dummy,
bacnet.object.primitivedata, 39
bacnet.object.properties, 40
bacnet.sandbox,44
```

58 Python Module Index

| A  | AnalogValueObject (class in bacnet.object.basic.general),  |
|--|--|
| ABLIB_Dummy (class in bac-                                   | 27   |
| net.object.hardware.terra.ablib_dummy),                      | api_create() (in module bacnet.webgui.bacnet_access), 52   |
| 36   | api_receive() (in module bacnet.webgui.bacnet_access),     |
| AbstractDaisy20 (class in bacnet.object.hardware.terra),     | 52   |
| 37   | api_transmit() (in module bacnet.webgui.bacnet_access),    |
| AbstractDaisy24Backlight (class in bac-                      | 53   |
| net.object.hardware.terra), 37                               | append() (bacnet.object.primitivedata.RingList method),    |
| AbstractDaisy24Button (class in bac-                         | 40   |
| net.object.hardware.terra), 38                               | application (bacnet.console.basic.BasicConsole at-         |
| AbstractDaisy24LCD (class in bac-                            | tribute), 19   |
| net.object.hardware.terra), 38                               | application (bacnet.system.BACnetSystem attribute), 48     |
| AccessCredentialObject (class in bac-                        | Application (class in bacnet.app.define), 12               |
| net.object.basic.general), 26                                | arg_object (bacnet.system.config.parser.FullArgumentParser |
| AccessDoorObject (class in bacnet.object.basic.general),     | attribute), 45   |
| 26   | AveragingObject (class in bacnet.object.basic.general),    |
| AccessPointObject (class in bacnet.object.basic.general),    | 27   |
| 26   | В  |
| AccessRightsObject (class in bac-                            | backled (bacnet.object.hardware.terra.ablib_dummy.Daisy24  |
| net.object.basic.general), 26                                | attribute), 37   |
| AccessUserObject (class in bacnet.object.basic.general),     | bacnet (module), 54  |
| 26   | bacnet.api (module), 3                                     |
| AccessZoneObject (class in bacnet.object.basic.general),     | bacnet.app (module), 12                                    |
| 26   | bacnet.app.basic (module), 11                              |
| AccumulatorObject (class in bacnet.object.basic.general), 26 | bacnet.app.define (module), 12                             |
| ActiveCovSubscriptionsProperty (class in bac-                | bacnet.app.handler (module), 7                             |
| net.object.properties), 40                                   | bacnet.app.handler.error (module), 4                       |
| adc_path (bacnet.object.hardware.terra.New_Daisy20 at-       | bacnet.app.handler.events (module), 4                      |
| tribute), 38   | bacnet.app.handler.fileaccess (module), 5                  |
| add_cov_subscription() (bac-                                 | bacnet.app.handler.objects (module), 5                     |
| net.app.handler.HandlerApplication method),                  | bacnet.app.handler.simple (module), 6                      |
| 7  | bacnet.console (module), 22                                |
| add_cov_subscription() (bac-                                 | bacnet.console.basic (module), 19                          |
| net.object.basic.general.Object method),                     | bacnet.console.creator (module), 16                        |
| 31   | bacnet.console.creator.events (module), 13                 |
| add_object() (bacnet.app.basic.BasicApplication              | bacnet.console.creator.fileaccess (module), 13             |
| method), 11  | bacnet.console.creator.local (module), 14                  |
| AnalogInputObject (class in bacnet.object.basic.general),    | bacnet.console.creator.objects (module), 15                |
| 27   | bacnet.console.creator.simple (module), 15                 |
| AnalogOutputObject (class in bac-                            | bacnet.console.define (module), 22                         |
| net.object.basic.general), 27                                | bacnet.console.parser (module), 18                         |
|  | bacnet.console.parser.events (module), 17                  |

| bacnet.console.parser.fileaccess (module), 17        |                      | BinaryWriteDummy (class in bac-                                 |
|--|----------------------|---|
| bacnet.console.parser.simple (module), 18            |                      | net.object.hardware.terra.ablib_dummy),                         |
| bacnet.debugging (module), 23                        |                      | 36  |
| bacnet.debugging.log (module), 22                    |                      | BitStringValueObject (class in bac-                             |
| bacnet.object (module), 43                           |                      | net.object.basic.general), 28                                   |
| bacnet.object.basic (module), 35                     |                      | breadcrumbs() (in module bacnet.webgui.control.views),          |
| bacnet.object.basic.cov_support (module), 24         |                      | 51  |
| bacnet.object.basic.device (module), 24              |                      | 31  |
| bacnet.object.basic.fileaccess (module), 25          |                      | C   |
| bacnet.object.basic.general (module), 26             |                      |   |
| bacnet.object.basic.program (module), 34             |                      | Calendar Object (class in bacnet.object.basic.general), 28      |
| bacnet.object.define (module), 39                    |                      | callback() (bacnet.console.basic.BasicConsole method),          |
|  |                      | 19  |
| bacnet.object.hardware (module), 38                  |                      | cast_value() (in module bacnet.console.creator.simple),         |
| bacnet.object.hardware.terra (module), 37            | 25                   | 15  |
| bacnet.object.hardware.terra.ablib_dummy (module),   | , 33                 | chan_file (bacnet.object.hardware.terra.New_Daisy20 at-         |
| bacnet.object.primitivedata (module), 39             |                      | tribute), 38  |
| bacnet.object.properties (module), 40                |                      | CharacterStringValueObject (class in bac-                       |
| bacnet.sandbox (module), 44                          |                      | net.object.basic.general), 28                                   |
| bacnet.sandbox.interface (module), 44                |                      | check_indication_queue() (bac-                                  |
| bacnet.settings (module), 54                         |                      | net.app.basic.BasicApplication method),                         |
| bacnet.system (module), 48                           |                      | 11  |
| bacnet.system.config (module), 45                    |                      | check_queue() (bacnet.app.basic.BasicApplication                |
| bacnet.system.config.helper (module), 45             |                      | method), 11   |
| bacnet.system.config.parser (module), 45             |                      | check_queue() (bacnet.console.basic.BasicConsole                |
| bacnet.system.managing (module), 47                  |                      | method), 19   |
| bacnet.system.vendors (module), 47                   |                      | check_remote_subscription_updates() (bac-                       |
| bacnet.system.version (module), 48                   |                      | net.app.handler.HandlerApplication method),                     |
| bacnet.webgui (module), 53                           |                      | 7   |
| bacnet.webgui.bacnet_access (module), 52             |                      | check_subscription_updates() (bac-                              |
| bacnet.webgui.control (module), 51                   |                      | net.app.handler.HandlerApplication method),                     |
| bacnet.webgui.control.templatetags (module), 50      |                      | 7   |
| bacnet.webgui.control.templatetags.menu (module),    | 50                   | <pre>client_manager() (in module bacnet.system.managing),</pre> |
| bacnet.webgui.control.urls (module), 51              |                      | 47  |
| bacnet.webgui.control.views (module), 51             |                      | close() (bacnet.debugging.log.MultiProcessingLog                |
| bacnet.webgui.manage (module), 53                    |                      | method), 23   |
| bacnet.webgui.webgui (module), 52                    |                      | cls_obj (in module bacnet.object.basic.general), 34             |
| bacnet.webgui.webgui.settings (module), 52           |                      | CommandObject (class in bacnet.object.basic.general),           |
| bacnet.webgui.webgui.settings.apps (module), 52      |                      | 28  |
| bacnet.webgui.webgui.settings.private (module), 52   |                      | ConfigManager (class in bacnet.system.config), 46               |
| bacnet.webgui.webgui.wsgi (module), 52               |                      | confirmation() (bacnet.app.basic.BasicApplication               |
| bacnet_debug() (in module bacnet.debugging), 23      |                      | method), 11   |
| BACnetAPI (class in bacnet.api), 3                   |                      | confirmed_cov_notification_request() (in module bac-            |
| BACnetSystem (class in bacnet.system), 48            |                      | net.console.parser.events), 17                                  |
| BasicApplication (class in bacnet.app.basic), 11     |                      | console (bacnet.system.BACnetSystem attribute), 48              |
| BasicConsole (class in bacnet.console.basic), 19     |                      | Console (class in bacnet.console.define), 22                    |
| BinaryInputObject (class in bacnet.object.basic.gene | eral).               | console_interrupt() (bacnet.app.basic.BasicApplication          |
| 27   | , , , ,              | method), 11   |
|  | bac-                 | console_interrupt() (bacnet.console.basic.BasicConsole          |
| net.object.basic.general), 27                        | · · · · <del>-</del> | method), 19   |
|  | bac-                 | console_interrupt() (bacnet.system.BACnetSystem                 |
| net.object.hardware.terra.ablib_dummy),              | · · · · <del>-</del> | method), 48   |
| 36   |                      | control_views_render() (in module bac-                          |
| BinaryValueObject (class in bacnet.object.basic.gene | eral).               | net.webgui.control.views), 51                                   |
| 27   |                      | non woo gone on the work, or                                    |

| $convert()(bacnet.object.hardware.terra.ablib\_dummy.Daisy$              |   |
|--|---|
| method), 36  | delete_cov_subscription() (bac-   |
| convert() (bacnet.object.hardware.terra.New_Daisy20 method), 38          | net.object.basic.general.Object method),<br>32                                |
| cov_supported() (bacnet.object.basic.general.Object                      | delete_cov_subscriptions() (bac-  |
| method), 31  | net.app.handler.HandlerApplication method),                                   |
| COVSubscription (class in bacnet.object.primitivedata),                  | 7   |
| 39   | delete_object() (bacnet.app.basic.BasicApplication                            |
| create() (bacnet.api.BACnetAPI method), 3                                | method), 11   |
| create_app() (in module bacnet.app), 13                                  | delete_request() (in module bac-  |
| create_console() (in module bacnet.console), 22                          | net.console.creator.objects), 15  |
| create_request() (in module bac-   | device (bacnet.console.basic.BasicConsole attribute), 19                      |
| net.console.creator.objects), 15   | DeviceObject (class in bacnet.object.basic.general), 29                       |
| create_version() (in module bacnet.system.version), 48                   | discover_hardware_objects() (in module bac-                                   |
| create_webgui() (in module bacnet.webgui), 53                            | net.object.hardware), 38  |
| CredentialDataInputObject (class in bac-                                 | DjangoProcess (class in bacnet.webgui), 53                                    |
| net.object.basic.general), 28  | do_AbortPDU() (bacnet.app.handler.HandlerApplication                          |
| CurrentDateProperty (class in bacnet.object.properties),                 | method), 7  |
| 41   | do_AbortPDU() (in module bacnet.app.handler.error), 4                         |
| CurrentTimeProperty (class in bacnet.object.properties),                 | do_AtomicReadFileRequest() (bac-  |
| 41   | net.app.handler.HandlerApplication method),                                   |
| D  | /   |
|  | do_AtomicReadFileRequest() (in module bac-                                    |
| Daisy11 (class in bac-   | net.app.handler.fileaccess), 5  |
| net.object.hardware.terra.ablib_dummy),                                  | do_AtomicWriteFileRequest() (bac-   |
| 36   | net.app.handler.HandlerApplication method),                                   |
| Daisy19 (class in bac-   | 8   |
| net.object.hardware.terra.ablib_dummy), 36                               | do_AtomicWriteFileRequest() (in module bac-<br>net.app.handler.fileaccess), 5 |
| Daisy20 (class in bac-   | do_buggers() (bacnet.console.basic.BasicConsole                               |
| net.object.hardware.terra.ablib_dummy),                                  | method), 19   |
| 36   | do_buggers() (bacnet.system.BACnetSystem method), 48                          |
| Daisy22 (class in bac-   | do_bugin() (bacnet.console.basic.BasicConsole method),                        |
| net.object.hardware.terra.ablib_dummy),                                  | 19  |
| 36   | do_bugout() (bacnet.console.basic.BasicConsole                                |
| Daisy24 (class in bac-   | method), 20   |
| net.object.hardware.terra.ablib_dummy),                                  | do_config() (bacnet.system.BACnetSystem method), 48                           |
| 36   | do_ConfirmedCOVNotificationRequest() (bac-                                    |
| data (bacnet.system.config.ConfigManager attribute), 46                  | net.app.handler.HandlerApplication method),                                   |
| DatePatternValueObject (class in bac-                                    | 8   |
| net.object.basic.general), 28  | do_ConfirmedCOVNotificationRequest() (in module bac-                          |
| DateTimePatternValueObject (class in bac-                                | net.app.handler.events), 4  |
| net.object.basic.general), 28  | do_ConfirmedEventNotificationRequest() (in module                             |
| DateTimeValueObject (class in bac-                                       | bacnet.app.handler.events), 4   |
| net.object.basic.general), 28  | do_CreateObjectRequest() (bac-  |
| DateValueObject (class in bacnet.object.basic.general),                  | net.app.handler.HandlerApplication method),                                   |
| 29   | 8   |
| decode() (bacnet.object.primitivedata.Remaining                          | do_CreateObjectRequest() (in module bac-                                      |
| method), 39  | net.app.handler.objects), 5   |
| default() (bacnet.console.basic.BasicConsole method), 19                 | do_DeleteObjectRequest() (bac-  |
| defaultProperties (bacnet.object.basic.device.LocalDeviceCattribute), 24 | Object net.app.handler.HandlerApplication method), 8                          |
| delete_cov_subscription() (bac-  | do_DeleteObjectRequest() (in module bac-                                      |
| net ann handler Handler Application method)                              | net.app.handler.objects). 5   |

| do_EOF() (bacnet.console.basic.BasicConsole method),   | 9   |
|--|---|
| 19   | do_SubscribeCOVRequest() (in module bac-  |
| do_Error() (bacnet.app.handler.HandlerApplication  | net.app.handler.events), 5  |
| method), 8   | do_UnconfirmedCOVNotificationRequest() (bac-                                    |
| do_Error() (in module bacnet.app.handler.error), 4   | net.app.handler.HandlerApplication method),                                     |
| do_exit() (bacnet.console.basic.BasicConsole method),  | 9   |
| 20   | do_UnconfirmedCOVNotificationRequest() (in module                               |
| do_gc() (bacnet.console.basic.BasicConsole method), 20   | bacnet.app.handler.events), 5   |
| do_GetEventInformationRequest() (in module bac-  | do_UnconfirmedEventNotificationRequest() (in module                             |
| net.app.handler.events), 4   | bacnet.app.handler.events), 5   |
| do_haltProgram() (bac-   | do_version() (bacnet.console.basic.BasicConsole                                 |
| net.object.basic.program.ExecProgramObject   | method), 20   |
| method), 35  | do_webgui() (bacnet.system.BACnetSystem method), 49                             |
| do_hardware() (bacnet.system.BACnetSystem method),   | do_WhoHasRequest() (bac-  |
| 49   | net.app.handler.HandlerApplication method),                                     |
| do_IAmRequest() (bac-  | 9 (C)                                       |
| net.app.handler.HandlerApplication method),  | do_WhoHasRequest() (in module bac-  |
| de IA mD a march (in marchala ha an at ann han dian ainmala)   | net.app.handler.simple), 6  |
| do_IAmRequest() (in module bacnet.app.handler.simple),   | do_WhoIsRequest() (bac-   |
| do_IHaveRequest() (bac-  | net.app.handler.HandlerApplication method),                                     |
| net.app.handler.HandlerApplication method),  | do_WhoIsRequest() (in module bac-   |
| net.app.nandier.rrandier.Application method),  | net.app.handler.simple), 6  |
| do_IHaveRequest() (in module bac-  | do_WritePropertyMultipleRequest() (bac-   |
| net.app.handler.simple), 6   | net.app.handler.HandlerApplication method),                                     |
| do_indication() (bacnet.app.handler.HandlerApplication   | g   |
| method), 9   | do_WritePropertyMultipleRequest() (in module bac-                               |
| do_info() (bacnet.console.basic.BasicConsole method),  | net.app.handler.simple), 6  |
| 20   | do_WritePropertyRequest() (bac-   |
| do_ReadPropertyMultipleRequest() (bac-   | net.app.handler.HandlerApplication method),                                     |
| net.app.handler.HandlerApplication method),  | 9   |
| 8  | do_WritePropertyRequest() (in module bac-                                       |
| do_ReadPropertyMultipleRequest() (in module bac-   | net.app.handler.simple), 6  |
| net.app.handler.simple), 6   | _   |
| do_ReadPropertyRequest() (bac-   | E   |
| net.app.handler.HandlerApplication method),  | emit() (bacnet.debugging.log.MultiProcessingLog                                 |
| 8  | method), 23   |
| do_ReadPropertyRequest() (in module bac-   | emptyline() (bacnet.console.basic.BasicConsole method),                         |
| net.app.handler.simple), 6   | 20  |
| do_RejectPDU() (bacnet.app.handler.HandlerApplication  | encode() (bacnet.object.primitivedata.Remaining                                 |
| method), 9   | method), 39   |
| do_RejectPDU() (in module bacnet.app.handler.error), 4<br>do_set_tag() (bacnet.system.BACnetSystem method), 49 | end_tr() (bacnet.system.vendors.TableParser method), 47                         |
| do_set_tag() (bacnet.system.bACnetsystem method), 49 do_shell() (bacnet.console.basic.BasicConsole method),    | EventEnrollmentObject (class in bac-  |
| do_shen() (bachet.console.basic.basicconsole method),  | net.object.basic.general), 29   |
| do_shell() (bacnet.system.BACnetSystem method), 49   | EventLogObject (class in bacnet.object.basic.general), 29                       |
| do_start() (bacnet.system.BACnetSystem method), 49   | ExecProgramObject (class in bac-  |
| do_SubscribeCOVPropertyRequest() (bac-   | net.object.basic.program), 34<br>exit() (bacnet.system.BACnetSystem method), 49 |
| net.app.handler.HandlerApplication method),  | exit() (bachet.system.bAchetsystem method), 49                                  |
| 9  | F   |
| do_SubscribeCOVPropertyRequest() (in module bac-   | filename (bacnet.system.config.ConfigManager attribute),                        |
| net.app.handler.events), 4   | 46  |
| do_SubscribeCOVRequest() (bac-   | FileObject (class in bacnet.object.basic.general), 29                           |
| net app handler Handler Application method)  | i neodject (class in dachet.object.basic.general), 29                           |

| first_value() (bacnet.object.primitivedata.RingList method), 40                                  | get_property() (bacnet.object.basic.general.Object method), 32  |
|--|---|
| format() (bacnet.debugging.log.LoggingFormatter method), 22                                      | get_sandbox_process() (in module bacnet.sandbox), 44 get_value() (bacnet.object.basic.general.Object method), |
| FullArgumentParser (class in bac-  | 32  |
| net.system.config.parser), 45  | get_vendors() (in module bacnet.system.vendors), 48   |
|  | get_version() (in module bacnet.system.version), 48   |
| G  | GlobalGroupObject (class in bacnet.object.basic.general),   |
| get() (bacnet.object.hardware.terra.ablib_dummy.BinaryRea<br>method), 36                         | ndDummy <sup>29</sup> GroupObject (class in bacnet.object.basic.general), 29                                  |
| get() (bacnet.object.hardware.terra.AbstractDaisy20 method), 37                                  | Н   |
| get() (bacnet.object.hardware.terra.AbstractDaisy24Backlig<br>method), 37                        | haltProgram() (bacnet.object.basic.program.ExecProgramObject method), 35                                      |
| get() (bacnet.object.hardware.terra.AbstractDaisy24Button method), 38                            | handle_data() (bacnet.system.vendors.TableParser method), 47  |
| get() (bacnet.object.hardware.terra.AbstractDaisy24LCD   | handle_remote_subscription() (bac-  |
| method), 38  | net.app.handler.HandlerApplication method),   |
| get() (bacnet.object.hardware.terra.New_Daisy20  | 10  |
| method), 38  | handle_starttag() (bacnet.system.vendors.TableParser  |
| get() (bacnet.object.properties.HardwareAccessObject   | method), 47<br>handle_td() (bacnet.system.vendors.TableParser method),  |
| method), 42 get() (bacnet.system.config.ConfigManager method), 46                                | 47  |
| get_crumb_name() (in module bac-   | HandlerApplication (class in bacnet.app.handler), 7   |
| net.webgui.control.views), 51  | hardware (bacnet.object.properties.HardwareAccessObject   |
| get_datatype() (in module bacnet.object.basic.general),  | attribute), 42  |
| 34   | HardwareAccessObject (class in bac-   |
| get_device() (bacnet.app.handler.HandlerApplication  | net.object.properties), 42  |
| method), 9   | help_create() (bacnet.console.basic.BasicConsole  |
| get_filename() (bacnet.object.basic.fileaccess.StreamAccess<br>method), 25                       | help_delete() (bacnet.console.basic.BasicConsole  |
| get_formatter() (in module bacnet.debugging), 24   | method), 21   |
| get_initial_object_list() (in module bacnet.object.define),                                      | help_iam() (bacnet.console.basic.BasicConsole method),  |
| 39   | 21  |
| get_input() (bacnet.system.config.ConfigManager method), 46                                      | help_ihave() (bacnet.console.basic.BasicConsole method), 21   |
| get_local_ip() (in module bacnet.system.config.helper), 45                                       | help_rdrec() (bacnet.console.basic.BasicConsole method), 21   |
| get_loggers() (in module bacnet.debugging), 24<br>get_names() (bacnet.console.basic.BasicConsole | help_rdstr() (bacnet.console.basic.BasicConsole method), 21   |
| method), 20  | help_read() (bacnet.console.basic.BasicConsole method),   |
| get_object_by_id() (bac-   | 21  |
| net.app.handler.HandlerApplication method), 10   | help_subscribe() (bacnet.console.basic.BasicConsole method), 21   |
| get_object_by_name() (bac-   | help_whohas() (bacnet.console.basic.BasicConsole  |
| net.app.handler.HandlerApplication method),  | method), 21   |
| 10   | help_whois() (bacnet.console.basic.BasicConsole   |
| get_object_class() (in module bac-   | method), 21   |
| net.object.basic.general), 34<br>get_object_id() (bacnet.app.handler.HandlerApplication          | help_write() (bacnet.console.basic.BasicConsole method), 21   |
| method), 10  | help_wrrec() (bacnet.console.basic.BasicConsole   |
| get_object_list() (in module bacnet.object), 43  | method), 21   |
|  | help_wrstr() (bacnet.console.basic.BasicConsole   |
|  | method), 21   |

| hysteresis() (bacnet.object.properties.HardwareAccessObject.properties.                                      | cLoopObject (class in bacnet.object.basic.general), 30  |
|--|---|
| method), 42  | M   |
| 1  | manager (bacnet.system.BACnetSystem attribute), 49  |
| iam_request() (in module bacnet.console.creator.simple), 15  | max_voltage (bacnet.object.hardware.terra.New_Daisy20 attribute), 38                                      |
| iam_request() (in module bacnet.console.parser.simple), 18   | ModuleLogger() (in module bacnet.debugging), 23<br>MultiProcessingLog (class in bacnet.debugging.log), 23 |
| identifier (bacnet.object.hardware.terra.ablib_dummy.ABLI attribute), 36                                     |   |
|  | MultiStateOutputObject (class in bacnet.object.basic.general), 30   |
| identifier (bacnet.object.hardware.terra.AbstractDaisy24But attribute), 38                                   |   |
| identifier (bacnet.object.hardware.terra.AbstractDaisy24LC attribute), 38                                    |   |
| ihave_request() (in module bac-<br>net.console.creator.simple), 15   | name (bacnet.object.hardware.terra.ablib_dummy.ABLIB_Dummy attribute), 36                                 |
| ihave_request() (in module bacnet.console.parser.simple),  | name (bacnet.object.hardware.terra.ablib_dummy.Daisy11 attribute), 36                                     |
| index() (in module bacnet.webgui.control.views), 51 indication() (bacnet.app.basic.BasicApplication method), | name (bacnet.object.hardware.terra.ablib_dummy.Daisy19 attribute), 36                                     |
| 11 IntegerValueObject (class in bacnet.object.basic.general),  | name (bacnet.object.hardware.terra.ablib_dummy.Daisy20 attribute), 36                                     |
| 29   | name (bacnet.object.hardware.terra.ablib_dummy.Daisy22  |
| iso_now() (in module bacnet.debugging), 24   | attribute), 36  |
| iter_objects() (bacnet.app.basic.BasicApplication method), 11  | name (bacnet.object.hardware.terra.ablib_dummy.Daisy24 attribute), 37                                     |
| J  | NetworkSecurityObject (class in bac-<br>net.object.basic.general), 31                                     |
| join() (bacnet.debugging.TimeoutJoinableQueue  | new_class (in module bacnet.object.basic.general), 34   |
| method), 23  | New_Daisy20 (class in bacnet.object.hardware.terra), 38   |
| L  | new_property() (in module bacnet.object.basic.general), 34  |
| LargeAnalogValueObject (class in bacnet.object.basic.general), 30  | NotificationClassObject (class in bac-<br>net.object.basic.general), 31                                   |
| last_value() (bacnet.object.primitivedata.RingList method), 40   | 0   |
| LifeSafetyPointObject (class in bac-   | Object (class in bacnet.object.basic.general), 31   |
| net.object.basic.general), 30  | ObjectIdentifierProperty (class in bac-   |
| LifeSafetyZoneObject (class in bac-  | net.object.properties), 42  |
| net.object.basic.general), 30<br>LoadControlObject (class in bacnet.object.basic.general),                   | ObjectPropertyReference (class in bac-  |
| 30   | net.object.primitivedata), 39<br>objectType (bacnet.object.basic.general.AccessCredentialObject           |
| loadProgram() (bacnet.object.basic.program.ExecProgramC method), 35  | Object attribute), 26   |
| local_list() (in module bacnet.console.creator.local), 14  | objectType (bacnet.object.basic.general.AccessDoorObject attribute), 26                                   |
| local_set() (in module bacnet.console.creator.local), 14   | objectType (bacnet.object.basic.general.AccessPointObject   |
| LocalDeviceObject (class in bacnet.object.basic.device), 24  | attribute), 26 objectType (bacnet.object.basic.general.AccessRightsObject                                 |
| lock_file() (bacnet.object.basic.fileaccess.StreamAccessFilemethod), 25                                      | eObject attribute), 26  |
| lock_subscriptions() (in module bacnet.app.handler), 10  | objectType (bacnet.object.basic.general.AccessUserObject attribute), 26                                   |
| LoggingFormatter (class in bacnet.debugging.log), 22   | autiouc), 20  |

- objectType (bacnet.object.basic.general.AccessZoneObject objectType (bacnet.object.basic.general.LifeSafetyZoneObject attribute), 26 attribute), 30
- objectType (bacnet.object.basic.general.AccumulatorObjectobjectType (bacnet.object.basic.general.LoadControlObject attribute), 27 attribute), 30
- objectType (bacnet.object.basic.general.AnalogInputObject objectType (bacnet.object.basic.general.LoopObject atattribute), 27 tribute), 30
- objectType (bacnet.object.basic.general.AnalogOutputObjectbjectType (bacnet.object.basic.general.MultiStateInputObject attribute), 27 attribute), 30
- objectType (bacnet.object.basic.general.AnalogValueObjectobjectType (bacnet.object.basic.general.MultiStateOutputObject attribute), 27 attribute), 30
- objectType (bacnet.object.basic.general.AveragingObject objectType (bacnet.object.basic.general.MultiStateValueObject attribute), 27 attribute), 31
- objectType (bacnet.object.basic.general.BinaryInputObject objectType (bacnet.object.basic.general.NetworkSecurityObject attribute), 27 attribute), 31
- objectType (bacnet.object.basic.general.BinaryOutputObjectbjectType (bacnet.object.basic.general.NotificationClassObject attribute), 27 attribute), 31
- objectType (bacnet.object.basic.general.BinaryValueObject objectType (bacnet.object.basic.general.OctetStringValueObject attribute), 27 attribute), 32
- objectType (bacnet.object.basic.general.BitStringValueObjectbjectType (bacnet.object.basic.general.PositiveIntegerValueObject attribute), 28 attribute), 32
- objectType (bacnet.object.basic.general.CalendarObject objectType (bacnet.object.basic.general.ProgramObject attribute), 28 attribute), 33
- objectType (bacnet.object.basic.general.CharacterStringValueObjectType (bacnet.object.basic.general.PulseConverterObject attribute), 28 attribute), 33
- objectType (bacnet.object.basic.general.CommandObject objectType (bacnet.object.basic.general.ScheduleObject attribute), 28 attribute), 33
- objectType (bacnet.object.basic.general.CredentialDataInput@bjectType (bacnet.object.basic.general.StructuredViewObject attribute), 28 attribute), 33
- objectType (bacnet.object.basic.general.DatePatternValueObjectType (bacnet.object.basic.general.TimePatternValueObject attribute), 28 attribute), 33
- objectType (bacnet.object.basic.general.DateTimePatternValore) by the (bacnet.object.basic.general.TimeValueObject attribute), 28 attribute), 33
- objectType (bacnet.object.basic.general.DateTimeValueObjectType (bacnet.object.basic.general.TrendLogMultipleObject attribute), 28 attribute), 33
- objectType (bacnet.object.basic.general.DateValueObject objectType (bacnet.object.basic.general.TrendLogObject attribute), 29 attribute), 33
- objectType (bacnet.object.basic.general.DeviceObject at- OctetStringValueObject (class in bactribute), 29 net.object.basic.general), 32
- objectType (bacnet.object.basic.general.EventEnrollmentObject() (bacnet.object.hardware.terra.ablib\_dummy.BinaryWriteDummy attribute), 29 method), 36
- objectType (bacnet.object.basic.general.EventLogObject off() (bacnet.object.hardware.terra.AbstractDaisy24Backlight attribute), 29 method), 37
- objectType (bacnet.object.basic.general.FileObject on() (bacnet.object.hardware.terra.ablib\_dummy.BinaryWriteDummy attribute), 29 method), 36
- objectType (bacnet.object.basic.general.GlobalGroupObjecton() (bacnet.object.hardware.terra.AbstractDaisy24Backlight attribute), 29 method), 37
- objectType (bacnet.object.basic.general.GroupObject atonecmd() (bacnet.console.basic.BasicConsole method), tribute), 29
- objectType (bacnet.object.basic.general.IntegerValueObject OptionalProperty (class in bacnet.object.properties), 42 attribute), 30
- objectType (bacnet.object.basic.general.LargeAnalogValueObject
  - attribute), 30 parse() (bacnet.api.BACnetAPI static method), 3
- objectType (bacnet.object.basic.general.LifeSafetyPointObjectre\_args() (bacnet.system.config.parser.FullArgumentParser attribute), 30 method), 45

| poll_hardware() (bacnet.object.basic.general.Object method), 32   | properties (bacnet.object.basic.general.CredentialDataInputObject attribute), 28  |
|---|---|
| poll_hardware() (in module bacnet.app.basic), 12<br>PositiveIntegerValueObject (class in bac-                     | properties (bacnet.object.basic.general.DatePatternValueObject attribute), 28     |
| net.object.basic.general), 32 postloop() (bacnet.console.basic.BasicConsole method),                              | properties (bacnet.object.basic.general.DateTimePatternValueObject attribute), 28 |
| 21  | properties (bacnet.object.basic.general.DateTimeValueObject                       |
| preloop() (bacnet.console.basic.BasicConsole method), 21  | attribute), 29 properties (bacnet.object.basic.general.DateValueObject            |
| pressed() (bacnet.object.hardware.terra.ablib_dummy.Dais method), 37  |   |
| print_text() (bacnet.console.basic.BasicConsole method),  | tribute), 29  |
| print_values() (in module bacnet.console.creator.local),  | properties (bacnet.object.basic.general.EventEnrollmentObject attribute), 29      |
| 14  | properties (bacnet.object.basic.general.EventLogObject                            |
| ProgramObject (class in bacnet.object.basic.general), 32 properties (bacnet.object.basic.device.LocalDeviceObject | attribute), 29<br>properties (bacnet.object.basic.general.FileObject at-          |
| attribute), 24 properties (bacnet.object.basic.general.AccessCredentialOl   | tribute), 29 bjprøperties (bacnet.object.basic.general.GlobalGroupObject          |
| attribute), 26  | attribute), 29  |
| properties (bacnet.object.basic.general.AccessDoorObject attribute), 26   | properties (bacnet.object.basic.general.GroupObject attribute), 29                |
| properties (bacnet.object.basic.general.AccessPointObject attribute), 26  | properties (bacnet.object.basic.general.IntegerValueObject attribute), 30         |
| properties (bacnet.object.basic.general.AccessRightsObjec   | t properties (bacnet.object.basic.general.LargeAnalogValueObject                  |
| attribute), 26 properties (bacnet.object.basic.general.AccessUserObject   | attribute), 30 properties (bacnet.object.basic.general.LifeSafetyPointObject      |
| attribute), 26  | attribute), 30 properties (bacnet.object.basic.general.LifeSafetyZoneObject       |
| attribute), 26  | attribute), 30  |
| properties (bacnet.object.basic.general.AccumulatorObject attribute), 27  | properties (bacnet.object.basic.general.LoadControlObject attribute), 30          |
| attribute), 27  | properties (bacnet.object.basic.general.LoopObject attribute), 30                 |
| attribute), 27  | etproperties (bacnet.object.basic.general.MultiStateInputObject attribute), 30    |
| properties (bacnet.object.basic.general.AnalogValueObject attribute), 27  | properties (bacnet.object.basic.general.MultiStateOutputObject attribute), 30     |
| properties (bacnet.object.basic.general.AveragingObject attribute), 27  | properties (bacnet.object.basic.general.MultiStateValueObject attribute), 31      |
|   | properties (bacnet.object.basic.general.NetworkSecurityObject attribute), 31      |
|   | t properties (bacnet.object.basic.general.NotificationClassObject attribute), 31  |
|   | properties (bacnet.object.basic.general.Object attribute), 32                     |
| properties (bacnet.object.basic.general.BitStringValueObjeattribute), 28  | cproperties (bacnet.object.basic.general.OctetStringValueObject attribute), 32    |
|   | properties (bacnet.object.basic.general.PositiveIntegerValueObject attribute), 32 |
| properties (bacnet.object.basic.general.CharacterStringValuattribute), 28   | nembjærties (bacnet.object.basic.general.ProgramObject attribute), 33             |
|   | properties (bacnet.object.basic.general.PulseConverterObject attribute), 33       |

|  | receive() (in module bacnet.sandbox.interface), 44  |
|--|---|
| attribute), 33   | receive_remote_notification() (bac-   |
| properties (bacnet.object.basic.general.StructuredViewObjeattribute), 33   | net.app.handler.HandlerApplication method),   |
| $properties \ (bacnet. object. basic. general. Time Pattern Value O') \\$  |   |
| attribute), 33   | RecordAccessFileObject (class in bac-   |
| properties (bacnet.object.basic.general.TimeValueObject  | net.object.basic.fileaccess), 25  |
| attribute), 33   | register_object_type() (in module bac-  |
| properties (bacnet.object.basic.general.TrendLogMultipleC  |   |
| attribute), 33   | Remaining (class in bacnet.object.primitivedata), 39  |
| properties (bacnet.object.basic.general.TrendLogObject attribute), 33  | attribute), 39  |
| Property (class in bacnet.object.properties), 43   | renew_cov_subscription() (bac-  |
| property_to_result() (in module bac-   | net.app.handler.HandlerApplication method),   |
| net.app.handler.simple), 6   | 10  |
|  | renew_cov_subscription() (bac-  |
| net.object.basic.general), 33  | net.object.basic.general.Object method),  |
| putstring() (bacnet.object.hardware.terra.ablib_dummy.Dai  |   |
| method), 37  | request() (bacnet.app.basic.BasicApplication method), 11 request_creator() (in module bacnet.console.creator), 17 |
| R  | response() (bacnet.app.basic.BasicApplication method),  |
|  | 12  |
| rdrec_request() (in module bac-<br>net.console.creator.fileaccess), 13   | response_parser() (in module bacnet.console.parser), 18   |
| rdstr_request() (in module bac-  | restart_on_failure() (in module bacnet.app.handler), 10   |
| net.console.creator.fileaccess), 13  | RingDict (class in bacnet.object.primitivedata), 39   |
| read_file_ack() (in module bac-  | RingList (class in bacnet.object.primitivedata), 40   |
| net.console.parser.fileaccess), 17   | run() (bacnet.app.basic.BasicApplication method), 12  |
| read_message() (in module bacnet.sandbox.interface), 44  | run() (bacnet.console.basic.BasicConsole method), 21  |
| read_property_ack() (in module bac-  | run() (bacnet.webgui.DjangoProcess method), 53  |
| net.console.parser.simple), 18   | run Program ()  (bacnet.object.basic.program. Exec Program Object   |
| read_property_any() (in module bac-  | method), 35   |
| net.app.handler.simple), 7   | C   |
| read_property_multiple_ack() (in module bac-   | S   |
| net.console.parser.simple), 18   | safe_delete() (bacnet.object.basic.program.ExecProgramObject  |
| read_request() (in module bacnet.console.creator.simple),  | method), 35   |
| 16   | sandbox_interact() (in module bacnet.sandbox), 44   |
| ReadableProperty (class in bacnet.object.properties), 43   | sandbox_support() (in module bacnet.sandbox), 45  |
| ReadFile() (bacnet.object.basic.fileaccess.RecordAccessFil   |   |
| method), 25 ReadFile() (bacnet.object.basic.fileaccess.StreamAccessFil   | send() (bacnet.api.BACnetAPI method), 3  • Cabride (bacnet.debugging.log.MultiProcessingLog                       |
| method), 25  | method), 23   |
| ReadProperty() (bacnet.object.basic.general.Object   |   |
| method), 31  | net.app.handler.HandlerApplication method),   |
| ReadProperty() (bacnet.object.properties.ActiveCovSubscr   |   |
| method), 40  | sequenceElements (bac-  |
| ReadProperty() (bacnet.object.properties.CurrentDateProperties.Cur |   |
| method), 41  | attribute), 39  |
| $ReadProperty() \ (bacnet.object.properties. CurrentTimeProperties) \ (bacnet.object.properties) \ (ba$ | estequenceElements (bac-  |
| method), 41  | net.object.primitivedata.ObjectPropertyReference  |
| ReadProperty() (bacnet.object.properties.Property  | attribute), 39  |
| method), 43  | server_manager() (in module bacnet.system.managing),  |
| receive() (bacnet.api.BACnetAPI method), 3   | 47  |
| receive() (bacnet.debugging.log.MultiProcessingLog method), 23   | set() (bacnet.object.properties.HardwareAccessObject method), 42  |

| set_application() (bacnet.object.basic.general.Object   |  |
|---|--|
| method), 32 set_application() (bacnet.object.basic.program.ExecProgram  | net.object.basic.general), 33<br>m <b>Dbjæl</b> togObject (class in bacnet.object.basic.general), 33                           |
| method), 35 set_debug() (in module bacnet.debugging), 24 set_bandler() (in module bacnet.debugging), 24                       | U  |
| set_handler() (in module bacnet.debugging), 24<br>set_value() (bacnet.object.basic.general.Object method),<br>32              | unconfirmed_cov_notification_request() (in module bacnet.console.parser.events), 17  |
| setcurpos() (bacnet.object.hardware.terra.ablib_dummy.Da method), 37  |  |
| setFormatter() (bacnet.debugging.log.MultiProcessingLog method), 23   | unlock_file() (bacnet.object.basic.fileaccess.StreamAccessFileObject method), 26   |
| shutdown() (bacnet.app.basic.BasicApplication method),  | Unsigned (class in bacnet.object.primitivedata), 40<br>update() (bacnet.system.config.parser.FullArgumentParser<br>method), 45 |
| shutdown() (bacnet.console.basic.BasicConsole method), 21   | update_devices() (bacnet.app.basic.BasicApplication method), 12  |
| shutdown() (bacnet.system.BACnetSystem method), 49 shutdown() (bacnet.webgui.DjangoProcess method), 53                        | url_attr() (in module bacnet.webgui.control.templatetags.menu), 50   |
| size (bacnet.object.primitivedata.RingDict attribute), 39 size (bacnet.object.primitivedata.RingList attribute), 40           | V  |
| StandardProperty (class in bacnet.object.properties), 43 start() (bacnet.system.config.ConfigManager method), 46              | valid() (bacnet.system.config.ConfigManager method), 46  |
| start_td() (bacnet.system.vendors.TableParser method), 47   | value (bacnet.object.hardware.terra.ablib_dummy.BinaryReadDummy attribute), 36   |
| stderr (bacnet.system.BACnetSystem attribute), 49<br>stdin (bacnet.system.BACnetSystem attribute), 49                         | value (bacnet.object.hardware.terra.AbstractDaisy24LCD attribute), 38  |
| stdout (bacnet.app.basic.BasicApplication attribute), 12 stdout (bacnet.system.BACnetSystem attribute), 49                    | verify_address() (bacnet.system.config.ConfigManager method), 46   |
| store() (bacnet.system.config.ConfigManager method), 46   | verify_bbmd() (bacnet.system.config.ConfigManager method), 46  |
| StreamAccessFileObject (class in bacnet.object.basic.fileaccess), 25  | volt_per_point (bacnet.object.hardware.terra.New_Daisy20 attribute), 38  |
| StructuredViewObject (class in bac-<br>net.object.basic.general), 33  | W  |
| subscribe_cov_property_request() (in module bac-<br>net.console.parser.events), 17<br>subscribe_cov_request() (in module bac- | watchdog() (bacnet.object.basic.program.ExecProgramObject method), 35  |
| subscribe_cov_request() (in module bac-<br>net.console.parser.events), 17<br>subscribe_request() (in module bac-              | whohas_request() (in module bac-<br>net.console.creator.simple), 16  |
| net.console.creator.events), 13   | whohas_request() (in module bac-<br>net.console.parser.simple), 18   |
| TableParser (class in bacnet.system.vendors), 47  | whois_request() (in module bac-<br>net.console.creator.simple), 16   |
| terminate() (bacnet.app.basic.BasicApplication method),   | whois_request() (in module bac-<br>net.console.parser.simple), 18  |
| terminate() (bacnet.console.basic.BasicConsole method),   | writable (bacnet.object.properties.HardwareAccessObject attribute), 42   |
| TimeoutJoinableQueue (class in bacnet.debugging), 23 TimePatternValueObject (class in bac-                                    | WritableProperty (class in bacnet.object.properties), 43<br>write() (bacnet.object.hardware.terra.AbstractDaisy24LCD           |
| net.object.basic.general), 33 TimeValueObject (class in bacnet.object.basic.general),   | method), 38 write_file_ack() (in module bac-   |
| transmit() (in module bacnet.sandbox.interface), 44   | net.console.parser.fileaccess), 17<br>write_message() (in module bacnet.sandbox.interface),<br>44                              |

```
write_request()
                        (in
                                   module
                                                    bac-
         net.console.creator.simple), 16
WriteFile() (bacnet.object.basic.fileaccess.RecordAccessFileObject
          method), 25
WriteFile() (bacnet.object.basic.fileaccess.StreamAccessFileObject
         method), 25
WriteProperty()
                     (bacnet.object.basic.general.Object
         method), 31
WriteProperty() (bacnet.object.basic.program.ExecProgramObject
         method), 34
Write Property () \ (bacnet.object.properties. Active Cov Subscriptions Property
         method), 40
WriteProperty() (bacnet.object.properties.CurrentDateProperty
         method), 41
WriteProperty() (bacnet.object.properties.CurrentTimeProperty
         method), 41
WriteProperty() (bacnet.object.properties.ObjectIdentifierProperty
         method), 42
WriteProperty()
                      (bacnet.object.properties.Property
         method), 43
                                    module
wrrec_request()
                        (in
                                                    bac-
         net.console.creator.fileaccess), 14
```

module

bac-

(in

net.console.creator.fileaccess), 14

wrstr\_request()